

# GAUSS<sup>TM</sup>

## *User Guide*

Information in this document is subject to change without notice and does not represent a commitment on the part of Aptech Systems, Inc. The software described in this document is furnished under a license agreement or nondisclosure agreement. The software may be used or copied only in accordance with the terms of the agreement. The purchaser may make one copy of the software for backup purposes. No part of this manual may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording, for any purpose other than the purchaser's personal use without the written permission of Aptech Systems, Inc.

©Copyright Aptech Systems, Inc. Maple Valley WA 1984-2005  
All Rights Reserved.

**GAUSS**, **GAUSS Engine** and **GAUSS Light** are trademarks of Aptech Systems, Inc.  
GEM is a trademark of Digital Research, Inc.  
Lotus is a trademark of Lotus Development Corp.  
HP LaserJet and HP-GL are trademarks of Hewlett-Packard Corp.  
PostScript is a trademark of Adobe Systems Inc.  
IBM is a trademark of International Business Machines Corporation  
Hercules is a trademark of Hercules Computer Technology, Inc.  
GraphiC is a trademark of Scientific Endeavors Corporation  
Tektronix is a trademark of Tektronix, Inc.  
Windows is a registered trademark of Microsoft Corporation.  
Other trademarks are the property of their respective owners.

Part Number: 005064

Version 7.0

Documentation Revision: 794      May 25, 2006

---

# Contents

## 1 Introduction

1.1	Product Overview . . . . .	1-1
1.2	Documentation Conventions . . . . .	1-2

## 2 Getting Started

2.1	Installation Under UNIX/Linux . . . . .	2-1
2.2	Installation Under Windows . . . . .	2-2
2.2.1	Machine Requirements . . . . .	2-2
2.2.2	Installation from Download . . . . .	2-2
2.2.3	Installation from CD . . . . .	2-3

## 3 Using the Command Line Interface

3.1	Viewing Graphics . . . . .	3-2
3.2	Interactive Commands . . . . .	3-2
3.2.1	quit . . . . .	3-2
3.2.2	ed . . . . .	3-3
3.2.3	browse . . . . .	3-3
3.2.4	config . . . . .	3-3
3.3	Debugging . . . . .	3-4
3.3.1	General Functions . . . . .	3-5
3.3.2	Listing Functions . . . . .	3-5
3.3.3	Execution Functions . . . . .	3-5
3.3.4	View Commands . . . . .	3-6
3.3.5	Breakpoint Commands . . . . .	3-7

## 4 Introduction to the Windows Interface

4.1	<b>GAUSS</b> Menus . . . . .	4-1
4.1.1	File Menu . . . . .	4-1

4.1.2	Edit Menu . . . . .	4-4
4.1.3	View Menu . . . . .	4-5
4.1.4	Configure Menu . . . . .	4-6
4.1.5	Run Menu . . . . .	4-6
4.1.6	Debug Menu . . . . .	4-7
4.1.7	Tools Menu . . . . .	4-8
4.1.8	Window Menu . . . . .	4-9
4.1.9	Help Menu . . . . .	4-10
4.1.10	<b>GAUSS</b> Toolbars . . . . .	4-10
4.1.11	Main Toolbar . . . . .	4-11
4.1.12	Working Directory Toolbar . . . . .	4-12
4.1.13	Debug Toolbar . . . . .	4-13
4.1.14	Window Toolbar . . . . .	4-14
4.1.15	Status Bar . . . . .	4-15
4.1.16	GAUSS Status . . . . .	4-15

## 5 Using the Windows Interface

5.1	Using the <b>GAUSS</b> Edit Windows . . . . .	5-1
5.1.1	Editing Programs . . . . .	5-2
5.1.2	Using Bookmarks . . . . .	5-2
5.1.3	Changing the Editor Properties . . . . .	5-2
5.1.4	Using Keystroke Macros . . . . .	5-2
5.1.5	Using Margin Functions . . . . .	5-3
5.1.6	Editing with Split Views . . . . .	5-3
5.1.7	Finding and Replacing Text . . . . .	5-3
5.1.8	Running Selected Text . . . . .	5-4
5.2	Using The Command Input - Output Window . . . . .	5-4
5.2.1	Running Commands . . . . .	5-4
5.2.2	Running Programs in Files . . . . .	5-5
5.3	Using Source View . . . . .	5-5
5.3.1	Source Tab . . . . .	5-6
5.3.2	Symbols Tab . . . . .	5-6

---

5.4	Using the Error Output Window . . . . .	5-7
5.5	Using The Debugger . . . . .	5-7
5.5.1	Starting and Stopping the Debugger . . . . .	5-7
5.5.2	Using Breakpoints . . . . .	5-8
5.5.3	Setting and Clearing Breakpoints . . . . .	5-8
5.5.4	Stepping Through a Program . . . . .	5-9
5.5.5	Viewing and Editing Variables . . . . .	5-9
5.6	Customizing <b>GAUSS</b> . . . . .	5-10
5.6.1	Preferences Dialog Box . . . . .	5-10
5.6.2	Editor Properties . . . . .	5-14
5.7	Using <b>GAUSS</b> Keyboard Assignments . . . . .	5-15
5.7.1	Cursor Movement Keys . . . . .	5-15
5.7.2	Edit Keys . . . . .	5-16
5.7.3	Text Selection Keys . . . . .	5-17
5.7.4	Command Keys . . . . .	5-17
5.7.5	Function Keys . . . . .	5-18
5.7.6	Menu Keys . . . . .	5-19

## 6 Matrix Editor

6.1	Using the Matrix Editor . . . . .	6-1
6.1.1	Editing Matrices . . . . .	6-1
6.1.2	Viewing Variables . . . . .	6-3
6.1.3	Matrix Editor Menu Bar . . . . .	6-3

## 7 Library Tool

7.1	Using the Library Tool . . . . .	7-1
7.1.1	Managing Libraries . . . . .	7-1
7.1.2	Managing the Library Index . . . . .	7-1
7.1.3	Managing Library Files . . . . .	7-3

---

## 8 GAUSS Source Browser

8.1	Using the Source Browser in TGAUSS . . . . .	8-1
8.2	Using the Source Browser in <b>GAUSS</b> . . . . .	8-2
8.2.1	Opening Files From the Source Browser . . . . .	8-4
8.2.2	Source Browser Keyboard Controls . . . . .	8-4

## 9 GAUSS Help

9.1	Help Menu . . . . .	9-1
9.2	Context-Sensitive Help . . . . .	9-1
9.3	SHIFT+F1 Support . . . . .	9-2
9.4	CTRL+F1 Support . . . . .	9-2
9.5	ToolTips . . . . .	9-3
9.6	Other Help . . . . .	9-3

## 10 Language Fundamentals

10.1	Expressions . . . . .	10-1
10.2	Statements . . . . .	10-2
10.2.1	Executable Statements . . . . .	10-3
10.2.2	Nonexecutable Statements . . . . .	10-3
10.3	Programs . . . . .	10-4
10.3.1	Main Section . . . . .	10-4
10.3.2	Secondary Sections . . . . .	10-5
10.4	Compiler Directives . . . . .	10-5
10.5	Procedures . . . . .	10-8
10.6	Data Types . . . . .	10-9
10.6.1	Constants . . . . .	10-9
10.6.2	Matrices . . . . .	10-11
10.6.3	N-dimensional Arrays . . . . .	10-18
10.6.4	Strings . . . . .	10-19
10.6.5	String Arrays . . . . .	10-23
10.6.6	Character Matrices . . . . .	10-25

---

10.6.7	Date and Time Formats . . . . .	10-26
10.6.8	Special Data Types . . . . .	10-27
10.7	Operator Precedence . . . . .	10-29
10.8	Flow Control . . . . .	10-31
10.8.1	Looping . . . . .	10-31
10.8.2	Conditional Branching . . . . .	10-34
10.8.3	Unconditional Branching . . . . .	10-35
10.9	Functions . . . . .	10-37
10.10	Rules of Syntax . . . . .	10-37
10.10.1	Statements . . . . .	10-37
10.10.2	Case . . . . .	10-38
10.10.3	Comments . . . . .	10-38
10.10.4	Extraneous Spaces . . . . .	10-38
10.10.5	Symbol Names . . . . .	10-39
10.10.6	Labels . . . . .	10-39
10.10.7	Assignment Statements . . . . .	10-39
10.10.8	Function Arguments . . . . .	10-40
10.10.9	Indexing Matrices . . . . .	10-40
10.10.10	Arrays of Matrices and Strings . . . . .	10-41
10.10.11	Arrays of Procedures . . . . .	10-42
 <b>11 Operators</b>		
11.1	Element-by-Element Operators . . . . .	11-1
11.2	Matrix Operators . . . . .	11-4
11.2.1	Numeric Operators . . . . .	11-4
11.2.2	Other Matrix Operators . . . . .	11-8
11.3	Relational Operators . . . . .	11-9
11.4	Logical Operators . . . . .	11-13
11.5	Other Operators . . . . .	11-16
11.6	Using Dot Operators with Constants . . . . .	11-21
11.7	Operator Precedence . . . . .	11-22

---

## 12 Procedures and Keywords

12.1	Defining a Procedure . . . . .	12-2
12.1.1	Procedure Declaration . . . . .	12-3
12.1.2	Local Variable Declarations . . . . .	12-3
12.1.3	Body of Procedure . . . . .	12-4
12.1.4	Returning from the Procedure . . . . .	12-5
12.1.5	End of Procedure Definition . . . . .	12-5
12.2	Calling a Procedure . . . . .	12-6
12.3	Keywords . . . . .	12-7
12.3.1	Defining a Keyword . . . . .	12-7
12.3.2	Calling a Keyword . . . . .	12-8
12.4	Passing Procedures to Procedures . . . . .	12-9
12.5	Indexing Procedures . . . . .	12-10
12.6	Multiple Returns from Procedures . . . . .	12-11
12.7	Saving Compiled Procedures . . . . .	12-13

## 13 Structures

13.1	Basic Structures . . . . .	13-1
13.1.1	Structure Definition . . . . .	13-1
13.1.2	Declaring an Instance . . . . .	13-2
13.1.3	Initializing an Instance . . . . .	13-3
13.1.4	Arrays of Structures . . . . .	13-4
13.1.5	Structure Indexing . . . . .	13-5
13.1.6	Saving an Instance to the Disk . . . . .	13-8
13.1.7	Loading an Instance from the Disk . . . . .	13-9
13.1.8	Passing Structures to Procedures . . . . .	13-9
13.2	Structure Pointers . . . . .	13-10
13.2.1	Creating and Assigning Structure Pointers . . . . .	13-10
13.2.2	Structure Pointer References . . . . .	13-11
13.2.3	Using Structure Pointers in Procedures . . . . .	13-13
13.3	Special Structures . . . . .	13-15



---

13.3.1	The DS Structure . . . . .	13-15
13.3.2	The PV Structure . . . . .	13-16
13.3.3	Miscellaneous PV Procedures . . . . .	13-20
13.3.4	Control Structures . . . . .	13-22
13.4	sqpSolvemt . . . . .	13-23
13.4.1	Input Arguments . . . . .	13-24
13.4.2	Output Argument . . . . .	13-27
13.4.3	Example . . . . .	13-29
13.4.4	The Command File . . . . .	13-30
 <b>14 Run-Time Library Structures</b>		
14.1	The PV Parameter Structure . . . . .	14-1
14.2	Fast Pack Functions . . . . .	14-6
14.3	The DS Data Structure . . . . .	14-7
 <b>15 N-Dimensional Arrays</b>		
15.1	Bracketed Indexing . . . . .	15-3
15.2	E×E Conformability . . . . .	15-5
15.3	Glossary of Terms . . . . .	15-5
 <b>16 Working with Arrays</b>		
16.1	Initializing Arrays . . . . .	16-1
16.1.1	areshape . . . . .	16-2
16.1.2	aconcat . . . . .	16-4
16.1.3	aeye . . . . .	16-6
16.1.4	arrayinit . . . . .	16-6
16.1.5	arrayalloc . . . . .	16-7
16.2	Assigning to Arrays . . . . .	16-8
16.2.1	index operator . . . . .	16-9
16.2.2	getArray . . . . .	16-12
16.2.3	getMatrix . . . . .	16-13

---

---

16.2.4	getMatrix4D . . . . .	16-13
16.2.5	getScalar3D, getScalar4D . . . . .	16-14
16.2.6	putArray . . . . .	16-15
16.2.7	setArray . . . . .	16-16
16.3	Looping with Arrays . . . . .	16-17
16.3.1	loopnextindex . . . . .	16-19
16.4	Miscellaneous Array Functions . . . . .	16-21
16.4.1	atranspose . . . . .	16-21
16.4.2	amult . . . . .	16-23
16.4.3	amean, amin, amax . . . . .	16-25
16.4.4	getDims . . . . .	16-27
16.4.5	getOrders . . . . .	16-27
16.4.6	arraytomat . . . . .	16-28
16.4.7	mattoarray . . . . .	16-28
16.5	Using Arrays with <b>GAUSS</b> functions . . . . .	16-28
16.6	A Panel Data Model . . . . .	16-32
16.7	Appendix . . . . .	16-35

## 17 Libraries

17.1	Autoloader . . . . .	17-1
17.1.1	Forward References . . . . .	17-2
17.1.2	The Autoloader Search Path . . . . .	17-3
17.2	Global Declaration Files . . . . .	17-9
17.3	Troubleshooting . . . . .	17-11
17.3.1	Using .dec Files . . . . .	17-12

## 18 Compiler

18.1	Compiling Programs . . . . .	18-2
18.1.1	Compiling a File . . . . .	18-2
18.2	Saving the Current Workspace . . . . .	18-2
18.3	Debugging . . . . .	18-3

---

## 19 File I/O

19.1	ASCII Files . . . . .	19-3
19.1.1	Matrix Data . . . . .	19-3
19.1.2	General File I/O . . . . .	19-6
19.2	Data Sets . . . . .	19-7
19.2.1	Layout . . . . .	19-7
19.2.2	Creating Data Sets . . . . .	19-8
19.2.3	Reading and Writing . . . . .	19-8
19.2.4	Distinguishing Character and Numeric Data . . . . .	19-9
19.3	<b>GAUSS</b> Data Archives . . . . .	19-11
19.3.1	Creating and Writing Variables to GDA's . . . . .	19-11
19.3.2	Reading Variables from GDA's . . . . .	19-12
19.3.3	Updating Variables in GDA's . . . . .	19-12
19.4	Matrix Files . . . . .	19-13
19.5	File Formats . . . . .	19-14
19.5.1	Small Matrix <b>v89</b> (Obsolete) . . . . .	19-15
19.5.2	Extended Matrix <b>v89</b> (Obsolete) . . . . .	19-16
19.5.3	Small String <b>v89</b> (Obsolete) . . . . .	19-16
19.5.4	Extended String <b>v89</b> (Obsolete) . . . . .	19-17
19.5.5	Small Data Set <b>v89</b> (Obsolete) . . . . .	19-17
19.5.6	Extended Data Set <b>v89</b> (Obsolete) . . . . .	19-19
19.5.7	Matrix <b>v92</b> (Obsolete) . . . . .	19-19
19.5.8	String <b>v92</b> (Obsolete) . . . . .	19-20
19.5.9	Data Set <b>v92</b> (Obsolete) . . . . .	19-21
19.5.10	Matrix <b>v96</b> . . . . .	19-22
19.5.11	Data Set <b>v96</b> . . . . .	19-23
19.5.12	<b>GAUSS</b> Data Archive . . . . .	19-24

## 20 Foreign Language Interface

20.1	Writing FLI Functions . . . . .	20-2
20.2	Creating Dynamic Libraries . . . . .	20-3

## 21 Data Transformations

21.1	Data Loop Statements . . . . .	21-2
21.2	Using Other Statements . . . . .	21-3
21.3	Debugging Data Loops . . . . .	21-3
21.3.1	Translation Phase . . . . .	21-3
21.3.2	Compilation Phase . . . . .	21-3
21.3.3	Execution Phase . . . . .	21-4
21.4	Reserved Variables . . . . .	21-4

## 22 Publication Quality Graphics

22.1	General Design . . . . .	22-1
22.2	Using <b>Publication Quality Graphics</b> . . . . .	22-2
22.2.1	Getting Started . . . . .	22-2
22.2.2	Graphics Coordinate System . . . . .	22-6
22.3	Graphic Panels . . . . .	22-7
22.3.1	Tiled Graphic Panels . . . . .	22-7
22.3.2	Overlapping Graphic Panels . . . . .	22-7
22.3.3	Nontransparent Graphic Panels . . . . .	22-8
22.3.4	Transparent Graphic Panels . . . . .	22-8
22.3.5	Using Graphic Panel Functions . . . . .	22-8
22.3.6	Inch Units in Graphic Panels . . . . .	22-10
22.3.7	Saving Graphic Panel Configurations . . . . .	22-10
22.4	Graphics Text Elements . . . . .	22-10
22.4.1	Selecting Fonts . . . . .	22-11
22.4.2	Greek and Mathematical Symbols . . . . .	22-12
22.5	Colors . . . . .	22-14
22.6	Global Control Variables . . . . .	22-14

## 23 ATOG

23.1	Command Summary . . . . .	23-1
23.2	Commands . . . . .	23-3

---

23.3	Examples . . . . .	23-12
23.4	Error Messages . . . . .	23-15

**24 Error Messages**

**25 Maximizing Performance**

25.1	Library System . . . . .	25-1
25.2	Loops . . . . .	25-2
25.3	Memory Usage . . . . .	25-3
25.3.1	Hard Disk Maintenance . . . . .	25-4
25.3.2	CPU Cache . . . . .	25-4

**A Fonts**

A.1	Simplex . . . . .	A-2
A.2	Simgrma . . . . .	A-3
A.3	Microb . . . . .	A-4
A.4	Complex . . . . .	A-5

**B Reserved Words Appendix**

**C Singularity Tolerance Appendix**

C.1	Reading and Setting the Tolerance . . . . .	C-2
C.2	Determining Singularity . . . . .	C-2

**26 Command Reference Introduction**

26.1	Documentation Conventions . . . . .	26-2
26.2	Command Components . . . . .	26-3
26.3	Using This Manual . . . . .	26-4
26.4	Global Control Variables . . . . .	26-5

26.4.1	Changing the Default Values . . . . .	26-5
26.4.2	The Procedure <b>gausset</b> . . . . .	26-6

## 27 Commands by Category

27.1	Mathematical Functions . . . . .	27-1
27.2	Finance Functions . . . . .	27-20
27.3	Matrix Manipulation . . . . .	27-22
27.4	N-Dimensional Array Handling . . . . .	27-27
27.5	Structures . . . . .	27-29
27.6	Data Handling (I/O) . . . . .	27-30
27.7	Compiler Control . . . . .	27-38
27.8	Program Control . . . . .	27-39
27.9	OS Functions and File Management . . . . .	27-44
27.10	Workspace Management . . . . .	27-45
27.11	Error Handling and Debugging . . . . .	27-46
27.12	String Handling . . . . .	27-47
27.13	Time and Date Functions . . . . .	27-49
27.14	Console I/O . . . . .	27-51
27.15	Output Functions . . . . .	27-52
27.16	Graphics . . . . .	27-53

## 28 Command Reference

### D Obsolete Commands

### E Colors

### Index

---

## List of Figures

4.1	<b>GAUSS</b> Graphical User Interface . . . . .	4-2
4.2	Main Toolbar . . . . .	4-11
4.3	Working Directory Toolbar . . . . .	4-12
4.4	Debug Toolbar . . . . .	4-13
4.5	Window Toolbar . . . . .	4-14
4.6	Status Bar . . . . .	4-15
6.1	Matrix Editor . . . . .	6-2
7.1	Library Tool . . . . .	7-2
8.1	Source Browser . . . . .	8-3
13.1	Structure tree for <b>e1</b> . . . . .	13-7





# Introduction 1

## 1.1 Product Overview

**GAUSS<sup>TM</sup>** is a complete analysis environment suitable for performing quick calculations, complex analysis of millions of data points, or anything in between. Whether you are new to computerized analysis or a seasoned programmer, the **GAUSS** family of products combine to offer you an easy to learn environment that is powerful and versatile enough for virtually any numerical task.

Since its introduction in 1984, **GAUSS** has been the standard for serious number crunching and complex modeling of large-scale data. Worldwide acceptance and use in government, industry, and the academic community is a firm testament to its power and versatility.

The **GAUSS** System can be described several ways: It is an exceptionally efficient number cruncher, a comprehensive programming language, and an interactive analysis environment. **GAUSS** may be the only numerical tool you will ever need.

## 1.2 Documentation Conventions

The following table describes how text formatting is used to identify **GAUSS** programming elements:

Text Style	Use	Example
regular text	narrative	“... text formatting is used ...”
<b>bold text</b>	emphasis	“ <b>...not supported under UNIX.</b> ”
<i>italic text</i>	variables	“... If <i>vnames</i> is a string or has fewer elements than <i>x</i> has columns, it will be ...”
monospace	code example  - or -	<pre>if scalerr(cm);     cm = inv(x); endif;</pre>
	filename, path, etc.	“...is located in the examples subdirectory...”
<b>monospace bold</b>	reference to a <b>GAUSS</b> command or other programming element within a narrative paragraph	“...as explained under <b>create...</b> ”
SMALL CAPS	reference to section of the manual	“...see OPERATOR PRECEDENCE, Section 11.7...”

# Getting Started 2

## 2.1 Installation Under UNIX/Linux

1. Make a directory to install **GAUSS** in.
2. **cd** to that directory.
3. Gunzip the `.gz` file if there is one.
4. Untar the `.tar` file.
5. Run the executable script `ginstall`.
6. Put the installation directory in the executable path.
7. Put the installation directory in the shared library search path.
8. Install the license. (To receive a license and license installation instructions, email [supportaptech.com](mailto:supportaptech.com).)

For last-minute information, see `README.term`.

## 2.2 Installation Under Windows

### 2.2.1 Machine Requirements

- A Pentium or AMD computer or equivalent.
- Operating System and Memory (RAM) requirements:
  - Windows NT4.0, SP6 IE4.0, 32 MB minimum 256 MB recommended.
  - Windows 2000, 64 MB minimum, 256 MB recommended.
  - Windows XP, 128 MB minimum, 256 MB recommended.
- Minimum of 100 MB free hard disk space, more may be needed depending on the size of matrices and the complexity of the program.
- Monthly defragmenting is recommended.

### 2.2.2 Installation from Download

#### Downloading

Please note that files can only be downloaded via **command line ftp**, NOT through a browser (such as Netscape, Internet Explorer, Firefox, etc.). You must use a command prompt window to download the files. To open a command prompt window, click on Start, then Run, and type **cmd**.

Note the directory that you are in; you may need to change to the directory where you wish to save the files. Use or make a directory for this that has no spaces in the title; there can be problems saving the files to a directory such as C:\Documents and Settings or C:\Program Files because of the spaces.

You must know the name of the files you wish to download. To download via command line ftp, first type the following at a command prompt:

```
ftp ftp.aptech.com
```

Log in as “anonymous” and use your email address as the password.

Then type the following at the ftp prompt to download the files:

```
get /outgoing/GAUSS_7.0_Win_32.zip GAUSS_7.0_Win_32.zip
get /outgoing/GAUSS_7.0_Manual.zip GAUSS_7.0_Manual.zip
bye
```

## Installation

Unzip GAUSS\_7.0\_Win\_32.zip in a temporary directory, and run setup.exe.

To receive a license and license installation instructions, email [supportaptech.com](mailto:supportaptech.com).

### 2.2.3 Installation from CD

Insert the **GAUSS 7.0** compact disc into the CD-ROM drive, and setup should start automatically. If setup does not start automatically, click Start, then click Run. Type D:\setup.exe in the dialog box (where D is the drive letter of the CD-ROM drive).

You can use this procedure for the initial installation of **GAUSS**, and for additions or modifications to **GAUSS** components.

To receive a license and license installation instructions, email [supportaptech.com](mailto:supportaptech.com).



# Using the Command Line Interface

# 3

TGAUSS is the command line version of **GAUSS**. The executable file, `tgauss` is located in the **GAUSS** installation directory.

The format for using TGAUSS is:

**tgauss** *flag(s) program program...*

- b** Execute file in batch mode and then exit. You can execute multiple files by separating file names with spaces.
- l logfile** Set the name of the batch mode log file when using the **-b** argument. The default is `tmp/gauss###.log`, where `###` is the process ID.
- e expression** Execute a **GAUSS** expression. This command is not logged when **GAUSS** is in batch mode.
- o** Suppress the sign-on banner (output only).
- T** Turn the dataloop translator on.
- t** Turn the dataloop translator off.

## 3.1 Viewing Graphics

GAUSS generates .tkf files for graphical output. The default output for graphics is `graphic.tkf`. On Windows, you can use `vwr.exe` to view the graphics file; on UNIX/Linux/Mac, you can use `vwrmp`. Two functions are available to convert .tkf files to PostScript for printing and viewing with external viewers: the **tkf2ps** function will convert .tkf files to PostScript (.ps) files, and the **tkf2eps** function will convert .tkf files to encapsulated PostScript (.eps) files. For example, to convert the file `graphic.tkf` to a postscript file named `graphic.ps` use:

```
ret = tkf2ps('filename.tkf', 'filename.ps')
```

If the function is successful it returns 0.

## 3.2 Interactive Commands

### 3.2.1 quit

The **quit** command will exit TGAUSS.

The format for **quit** is:

```
quit
```

You can also use the **system** command to exit TGAUSS from either the command line or a program (see **system** in the GAUSS LANGUAGE REFERENCE).

The format for **system** is:

```
system
```



### 3.2.2 ed

The **ed** command will open an input file in an external text editor (see **ed** in the GAUSS LANGUAGE REFERENCE).

The format for **ed** is:

*ed filename*

### 3.2.3 browse

The **browse** command allows you to search for specific symbols in a file and open the file in the default editor. You can use wildcards to extend search capabilities of the **browse** command.

The format for **browse** is:

*browse symbol*

### 3.2.4 config

The **config** command gives you access to the configuration menu allowing you to change the way GAUSS runs and compiles files.

The format for **config** is:

*config*

## Run Menu

### Translator

Toggles on/off the translation of a file using **dataloop**. The translator is not necessary for GAUSS program files not using **dataloop**.

<b>Translator line number tracking</b>	Toggles on/off execution time line number tracking of the original file before translation.
<b>Line number tracking</b>	Toggles on/off the execution time line number tracking. If the translator is on, the line numbers refer to the translated file.

### Compile Menu

<b>Autoload</b>	Toggles on/off the autoloader.								
<b>Autodelete</b>	Toggles on/off autodelete.								
<b>GAUSS Library</b>	Toggles on/off the <b>GAUSS</b> library functions.								
<b>User Library</b>	Toggles on/off the user library functions.								
<b>Declare Warnings</b>	Toggles on/off the declare warning messages during compiling.								
<b>Compiler Trace</b>	Includes the following options: <table><tr><td><b>Off</b></td><td>Turns off the compiler trace function.</td></tr><tr><td><b>File</b></td><td>Traces program file openings and closings.</td></tr><tr><td><b>Line</b></td><td>Traces compilation by line.</td></tr><tr><td><b>Symbol</b></td><td>Creates a report of procedures and the local and global symbols they reference.</td></tr></table>	<b>Off</b>	Turns off the compiler trace function.	<b>File</b>	Traces program file openings and closings.	<b>Line</b>	Traces compilation by line.	<b>Symbol</b>	Creates a report of procedures and the local and global symbols they reference.
<b>Off</b>	Turns off the compiler trace function.								
<b>File</b>	Traces program file openings and closings.								
<b>Line</b>	Traces compilation by line.								
<b>Symbol</b>	Creates a report of procedures and the local and global symbols they reference.								

## 3.3 Debugging

The **debug** command runs a program under the source level debugger.

The format for **debug** is:

`debug filename`

### 3.3.1 General Functions

<b>?</b>	Displays a list of available commands.
<b>q/Esc</b>	Exits the debugger and returns to the <b>GAUSS</b> command line.
<b>+/-</b>	Disables the last command repeat function.

### 3.3.2 Listing Functions

<b>l</b> <i>number</i>	Displays a specified number of lines of source code in the current file.
<b>lc</b>	Displays source code in the current file starting with the current line.
<b>ll</b> <i>file line</i>	Displays source code in the named file starting with the specified line.
<b>ll</b> <i>file</i>	Displays source code in the named file starting with the first line.
<b>ll</b> <i>line</i>	Displays source code starting with the specified line. File does not change.
<b>ll</b>	Displays the next page of source code.
<b>lp</b>	Displays the previous page of source code.

### 3.3.3 Execution Functions

<b>s</b> <i>number</i>	Executes the specified number of lines, stepping over procedures.
<b>i</b> <i>number</i>	Executes the specified number of lines, stepping into procedures.
<b>x</b> <i>number</i>	Executes code from the beginning of the program to the specified line count, or until a breakpoint is hit.
<b>g</b> <i>[[args]]</i>	Executes from the current line to the end of the program, stopping at breakpoints. The optional arguments specify other stopping points. The syntax for each optional argument is:

*filename line period* The debugger will stop every *period* times it reaches the specified *line* in the named file.

<i>filename line</i>	The debugger will stop when it reaches the specified <i>line</i> in the named file.
<i>filename ,, period</i>	The debugger will stop every <i>period</i> times it reaches any line in the named file.
<i>line period</i>	The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the current file.
<i>filename</i>	The debugger will stop at every line in the named file.
<i>line</i>	The debugger will stop when it reaches the specified <i>line</i> in the current file.
<i>procedure period</i>	The debugger will stop every <i>period</i> times it reaches the first line in a called procedure.
<i>procedure</i>	The debugger will stop every time it reaches the first line in a called procedure.
<b>j</b> <i>[[args]]</i>	Executes code to a specified line, procedure, or period in the file without stopping at breakpoints. The optional arguments are the same as <b>g</b> , listed above.
<b>jx</b> <i>number</i>	Executes code to the execution count specified ( <i>number</i> ) without stopping at breakpoints.
<b>o</b>	Executes the remainder of the current procedure (or to a breakpoint) and stops at the next line in the calling procedure.

### 3.3.4 View Commands

<b>v</b> <i>[[vars]]</i>	Searches for (a local variable, then a global variable) and displays the value of a specified variable.
<b>v\$</b> <i>[[vars]]</i>	Searches for (a local variable, then a global variable) and displays the specified character matrix.

The display properties of matrices and string arrays can be set using the following commands.

<b>r</b>	Specifies the number of rows to be shown.
----------	---

---

<b>c</b>	Specifies the number of columns to be shown.
<b>num,num</b>	Specifies the indices of the upper left corner of the block to be shown.
<b>w</b>	Specifies the width of the columns to be shown.
<b>p</b>	Specifies the precision shown.
<b>f</b>	Specifies the format of the numbers as decimal, scientific, or auto format.
<b>q</b>	Quits the matrix viewer.

### 3.3.5 Breakpoint Commands

<b>lb</b>	Shows all the breakpoints currently defined.																
<b>b</b> <code>[[args]]</code>	Sets a breakpoint in the code. The syntax for each optional argument is: <table> <tr> <td><i>filename line period</i></td><td>The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the named file.</td></tr> <tr> <td><i>filename line</i></td><td>The debugger will stop when it reaches the specified <i>line</i> in the named file.</td></tr> <tr> <td><i>filename ,, period</i></td><td>The debugger will stop every <i>period</i> times it reaches any line in the named file.</td></tr> <tr> <td><i>line period</i></td><td>The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the current file.</td></tr> <tr> <td><i>filename</i></td><td>The debugger will stop at every line in the named file.</td></tr> <tr> <td><i>line</i></td><td>The debugger will stop when it reaches the specified line in the current file.</td></tr> <tr> <td><i>procedure period</i></td><td>The debugger will stop every <i>period</i> times it reaches the first line in a called procedure.</td></tr> <tr> <td><i>procedure</i></td><td>The debugger will stop every time it reaches the first line in a called procedure.</td></tr> </table>	<i>filename line period</i>	The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the named file.	<i>filename line</i>	The debugger will stop when it reaches the specified <i>line</i> in the named file.	<i>filename ,, period</i>	The debugger will stop every <i>period</i> times it reaches any line in the named file.	<i>line period</i>	The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the current file.	<i>filename</i>	The debugger will stop at every line in the named file.	<i>line</i>	The debugger will stop when it reaches the specified line in the current file.	<i>procedure period</i>	The debugger will stop every <i>period</i> times it reaches the first line in a called procedure.	<i>procedure</i>	The debugger will stop every time it reaches the first line in a called procedure.
<i>filename line period</i>	The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the named file.																
<i>filename line</i>	The debugger will stop when it reaches the specified <i>line</i> in the named file.																
<i>filename ,, period</i>	The debugger will stop every <i>period</i> times it reaches any line in the named file.																
<i>line period</i>	The debugger will stop every <i>period</i> times it reaches the specified <i>line</i> in the current file.																
<i>filename</i>	The debugger will stop at every line in the named file.																
<i>line</i>	The debugger will stop when it reaches the specified line in the current file.																
<i>procedure period</i>	The debugger will stop every <i>period</i> times it reaches the first line in a called procedure.																
<i>procedure</i>	The debugger will stop every time it reaches the first line in a called procedure.																
<b>d</b> <code>[[args]]</code>	Removes a previously specified breakpoint. The optional arguments are the same arguments as <b>b</b> , listed above.																



# Introduction to the Windows Interface

# 4

The **GAUSS** graphical user interface is a multiple document interface. The interface consists of the Menu Bar, the Toolbar, edit windows, the Command Input-Output window, and the Status bar (see Figure 4.1).

## 4.1 GAUSS Menus

You can view the commands on a menu by either clicking the menu name or pressing ALT+*n*, where *n* is the underlined letter in the menu name. For example, to display the File menu, you can either click File or press ALT+F.

### 4.1.1 File Menu

The File menu lets you access the file, printer setup, and exit commands. Some of these actions can also be executed from the toolbar. The File menu contains the following commands:




Figure 4.1: **GAUSS** Graphical User Interface



---

<b>New</b>	Opens a new, untitled document in an Edit window. <i>Note: New, unsaved documents are not automatically backed up until you save them, giving them a file name.</i>
<b>Open</b>	Opens an existing file for viewing or editing.
<b>Reload</b>	Updates the active file.
<b>Save</b>	Saves your changes to the file in the active window. If the file is untitled, you are prompted for a path and filename.
<b>Save As</b>	Saves your changes to the file in the active window using a new or different path or file name.
<b>Close</b>	Closes the document in the active window. You are prompted to save the file if it has been modified since you last saved it.
<b>Close All</b>	Closes all open files. You are prompted to save any file that has been modified since you last saved it.
<b>Run Program</b>	Runs a <b>GAUSS</b> program file.
<b>Insert File</b>	Opens an existing text file and copies the contents into the active document. This is similar to pasting text from the Windows clipboard.
<b>Print</b>	Prints the active file or selected text from the active window.
<b>Print Setup</b>	Specifies the printer you want to use. Other printer options, such as page orientation and paper tray, are also accessed with this command.
<b>Properties</b>	Displays information about the active file.
<b>Change Working Directory</b>	Changes the directory where <b>GAUSS</b> looks for the files it uses for normal operation. This command does not affect the Open or Save As paths.
<b>Clear Working Directory List</b>	Clears the working directory list.
<b>Exit</b>	Closes all open files and exits <b>GAUSS</b> . You are prompted to save any file that has been modified since it was last saved.
<b>Recent Files</b>	<b>GAUSS</b> maintains a list of the ten most recent files you opened, at the end of the File menu. If the file you want to open is on this list, click it and <b>GAUSS</b> opens it in an Edit window.

---

### 4.1.2 Edit Menu

The Edit menu lets you access the set of editing commands. Some of these actions can also be executed from the toolbar. The Edit menu contains the following commands:

<b>Undo</b>	Restores your last changes in the active window.
<b>Redo</b>	Restores changes in the active window that you removed using the Undo Edit command.
<b>Cut</b>	Removes selected text from the active window and places it on the Windows clipboard.
<b>Copy</b>	Copies selected text from the active window to the Windows clipboard.
<b>Paste</b>	Copies text from the Windows clipboard to the active window at the cursor position.
<b>Select All</b>	Selects all text in the active window.
<b>Clear All</b>	Clears all text in the active window
<b>Find</b>	Finds the specified text in the active window. The search starts at the cursor position and continues to the end of the text in the active window. The search can be case sensitive or case insensitive. You may also limit the search to regular expressions.
<b>Find Again</b>	Resumes the search for the next occurrence of the text you specified in the previous Find action. Subsequent searches for the same text can also be performed by pressing F3.
<b>Replace</b>	Locates the specified text in the active window and replaces it with the text you entered in the “Replace with” field in the Search dialog box. The search starts at the cursor position and continues to the end of the text in the active window. The search can be case sensitive or case insensitive, and the replacement can be unique or global.
<b>Insert Time/Date</b>	Inserts the current time and date at the cursor position. <b>GAUSS</b> uses the time and date that appears in the Microsoft Windows Date/Time Properties window.

---

<b>Go To Line</b>	Moves the cursor to the specified line number.
<b>Go To Next Bookmark</b>	Moves to the next bookmark in the program.
<b>Toggle Bookmark</b>	Sets or clears existing bookmarks from the program.
<b>Edit Bookmarks</b>	Opens the Edit Bookmarks window. From the Edit Bookmarks window you can add, remove, or go to any set bookmark in a program.
<b>Record Macro</b>	Places a series of keystrokes into memory so that they can be called at a later date. For more information about recording macros see USING KEYSTROKE MACROS, Section 5.1.4.
<b>Clear Macros</b>	Clears macros from memory.

### 4.1.3 View Menu

The View menu lets you toggle the Main Toolbar, the Status Bar, the Working Directory Toolbar, and the Debug Toolbar on or off.

<b>Main Toolbar</b>	Toggles the Main toolbar on or off. For more information about the Main toolbar, see MAIN TOOLBAR, Section 4.1.11.
<b>Status Bar</b>	The Status Bar is located along the bottom of the <b>GAUSS</b> window. For more information about the status bar, see STATUS BAR, Section 4.1.15.
<b>Working Directory</b>	Toggles the Working Directory toolbar on or off. For more information about the working directory toolbar, see WORKING DIRECTORY TOOLBAR, Section 4.1.12.
<b>Debug Toolbar</b>	Toggles the Debug toolbar on or off. For more information about the Debug toolbar, see DEBUG TOOLBAR, Section 4.1.13.
<b>Window Toolbar</b>	Toggles the Window toolbar on or off. For more information about the Window toolbar, see WINDOW TOOLBAR, Section 4.1.14.
<b>Error Output</b>	Opens or closes the Error Output window.
<b>Source View</b>	Displays or undisplay the Source/Symbols window.

---

### 4.1.4 Configure Menu

The Configure menu lets you customize the **GAUSS** environment.

<b>Preferences</b>	Opens the General Preferences window. From the General Preferences window you can define Run options, Compile options, DOS window options, and Autosave options. For more information on configuring <b>GAUSS</b> General Preferences, see PREFERENCES DIALOG BOX, Section 5.6.1.
<b>Editor Properties</b>	Opens the Editor Properties window. From the Editor Properties window you can define colors and fonts, the language syntax, tabs, or general editor properties. For more information on configuring editor properties, see EDITOR PROPERTIES, Section 5.6.2.

### 4.1.5 Run Menu

The Run menu lets you run the code you have entered, a block of code you selected, or the active file, depending on the operating mode.

<b>Insert GAUSS Prompt</b>	Manually adds the <b>GAUSS</b> prompt (>>) at the cursor position. The <b>GAUSS</b> prompt is automatically displayed following the execution of <b>GAUSS</b> code.
<b>Insert Last Cmd</b>	Re-enters the last command written to the Input buffer.
<b>Run Selected Text</b>	Runs any text selected from the editor or the Command Input-Output window.
<b>Run Active File</b>	Runs the active file. The file then becomes the main file.
<b>Test Compile Active File</b>	Compiles the currently selected file. During compilation, any errors are displayed in the Output window. <i>Note: This command is different than the <b>GAUSS compile</b> command, which compiles a program and saves the pseudocode as a file.</i>
<b>Run Main File</b>	Runs the file specified in the Main File list.
<b>Test Compile</b>	Test compiles the main file. During compilation, any errors are displayed in

---

<b>Main File</b>	the Output window. <i>Note: This command is different than the <b>GAUSS compile</b> command, which compiles a program and saves the pseudocode as a file.</i>
<b>Edit Main File</b>	Opens the specified main file in an edit window.
<b>Stop Program</b>	Stops the program currently running and returns control to the editor.
<b>Build GCG File from Main</b>	Creates <b>GAUSS</b> pseudocode file that can be run over and over with no compile time.
<b>Set Main File</b>	Makes the active file the main file.
<b>Clear Main File List</b>	Removes all entries in the Main File list on the Main toolbar.
<b>Translate Dataloop Cmds</b>	Toggles translate dataloop command on and off. For more information see DATA TRANSFORMATIONS, Chapter 21.

#### 4.1.6 Debug Menu

The Debug menu lets you access the commands used to debug your active file or main file.

The Debug menu contains the following Commands:

<b>Debug Main File</b>	Runs the main file in the debugger.
<b>Debug Active File</b>	Runs the active file in the debugger.
<b>Set/Clear Breakpoint</b>	Enables or disables a breakpoint at the cursor in the active file.
<b>Edit Breakpoints</b>	Opens a list of all breakpoints in your program. The breakpoints are listed by line number. Any procedure breakpoints are also listed.
<b>Clear All Breakpoints</b>	Removes all line and procedure breakpoints from the active file.

---

<b>Go</b>	Starts the debugger.
<b>Stop</b>	Stops the debugger.
<b>Run to Cursor</b>	Runs the program until it reaches the cursor position.
<b>Step Into</b>	Runs the next executable line of code in the application and steps into procedures.
<b>Step Over</b>	Runs the next executable line of code in the application but does not step into procedures.
<b>Step Out</b>	Runs the remainder of the current procedure and stops at the next line in the calling procedure. Step Out returns if a breakpoint is encountered.
<b>Set Watch</b>	Opens the Matrix Editor for watching changing variable data. For more information about viewing variables see <a href="#">VIEWING VARIABLES</a> , Section <a href="#">5.5.5</a> .

### 4.1.7 Tools Menu

The Tools menu lets you open **GAUSS** tools windows. The following commands can be used:

<b>Matrix Editor</b>	Lets you create or edit data in a matrix (or grid). A cell can be edited by typing in a new value and pressing ENTER. For more information see <a href="#">MATRIX EDITOR</a> , Chapter <a href="#">6</a> .
<b>Graphics Editor</b>	Opens the Graphics Editor, which is an interactive TKF file editor. This menu item will be inactive if you have not purchased the Graphics Editor.
<b>Source Browser</b>	Searches source files for string patterns. For more information see <a href="#">GAUSS SOURCE BROWSER</a> , Chapter <a href="#">8</a> .
<b>Lib Tool</b>	Lets you manage the contents of libraries. For more information see <a href="#">LIBRARY TOOL</a> , Chapter <a href="#">7</a> .
<b>DOS Compatibility Window</b>	Opens a DOS Compatibility window.

### 4.1.8 Window Menu

The Window menu commands let you manage your workspace. You can toggle the focus between all open windows using CTRL+TAB, or clicking in the window you want active. All open windows are listed at the end of the Window menu. The following commands can be used:

<b>Cmd Window</b>	Makes the Command Input - Output window the active window.
<b>Output Window</b>	Splits the output from the Command Input - Output window.
<b>Debug Window</b>	Starts the debugger on the current file.
<b>Re-use Window</b>	If checked, the next file browsed in the Source Browser will be displayed in the same window.
<b>Command Log</b>	Loads the command log window into an editor.
<b>Close All Graphics</b>	Closes all TKF File Viewer windows.
<b>Dual Horizontal</b>	Horizontally tiles the program source and execution windows within the main window, and minimizes all other windows.
<b>Dual Vertical</b>	Vertically tiles the program source and execution windows within the main window, and minimizes all other windows.
<b>Cascade</b>	Arranges all open windows on the screen, overlapping each, with the active window on top.
<b>Tile Horizontal</b>	Arranges all open windows horizontally on the screen without any overlap.
<b>Tile Vertical</b>	Arranges all open windows vertically on the screen without any overlap.
<b>Arrange Icons</b>	Arranges all minimized windows across the bottom of the main <b>GAUSS</b> window.
<b>Split Horizontally</b>	<p>Splits the active window into two horizontal panes. This allows you to view two different areas of the same document to facilitate split-window editing.</p> <p><i>Note: You can move the splitter bar by dragging it with the mouse. You can remove the splitter bar from the window by dragging it to the end of the window.</i></p>

<b>Split Vertically</b>	Splits the active window into two vertical panes. This allows you to view two different areas of the same document to facilitate split-window editing.  <i>Note: You can move the splitter bar by dragging it with the mouse. You can remove the splitter bar from the window by dragging it to the end of the window.</i>
<b>Open Window List</b>	<b>GAUSS</b> maintains a list of all the windows you have opened at the end of the Window menu. If the window you want to view is on this list, click it and it becomes the active window.

### 4.1.9 Help Menu

The Help menu lets you access information in the **GAUSS** Help system. The **GAUSS** Help menu contains the following Commands:

<b>User's Guide</b>	Accesses the online <b>GAUSS</b> USER'S GUIDE.
<b>Keyboard</b>	Accesses the list of keystrokes you can use for cursor movement, editing, and text selection.
<b>Reference</b>	Accesses the online <b>GAUSS</b> LANGUAGE REFERENCE, which contains the syntax for each <b>GAUSS</b> command.
<b>Tip of the Day</b>	Displays a tip to help you make better use of the features available in the <b>GAUSS</b> Windows Interface.
<b>About GAUSS...</b>	Provides information about your version of <b>GAUSS</b> , your license type and ID, as well as copyright information.

### 4.1.10 GAUSS Toolbars

The toolbar buttons let you have fast access to the most commonly used commands. Place the mouse pointer over the button to display a description of the command.






Figure 4.2: Main Toolbar

#### 4.1.11 Main Toolbar

<b>New</b>	Opens a new, untitled document in an Edit window. <i>Note: New, unsaved documents are not automatically backed up until you save them, giving them a file name.</i>
<b>Open</b>	Opens an existing file for viewing or editing.
<b>Save</b>	Saves your changes to the file in the active window. If the file is untitled, you are prompted for a path and filename.
<b>Cut</b>	Removes selected text from the active window and places it on the Windows clipboard.
<b>Copy</b>	Copies selected text from the active window to the Windows clipboard.
<b>Paste</b>	Copies text from the Windows clipboard to the active window at the cursor position.
<b>Print</b>	Prints the active file or selected text from the active window.
<b>Help</b>	Accesses the <b>GAUSS</b> help system.
<b>Source Browser</b>	Opens the <b>GAUSS</b> Source Browser, which allows you to search for symbols in a specified file or directory. For more information, see <b>GAUSS SOURCE BROWSER</b> , Chapter 8.

<b>Graphics Editor</b>	Opens the Graphics Editor, which is an interactive TKF file editor. This menu item will be inactive if you have not purchased the Graphics Editor.
<b>Run Selected Text</b>	Runs any text selected from the editor or the Command Input-Output window.
<b>Run Active File</b>	Runs the active file. The file then becomes the main file.
<b>Main File List</b>	Displays the name of the main file and lets you quickly change the main file to one of the files listed.
<b>Run Main File</b>	Runs the file specified in the Main File list.
<b>Stop Program</b>	Stops the program currently running and returns control to the editor.
<b>Test Compile Main File</b>	Compiles the main file. During compilation, any errors are displayed in the Output window.  <i>Note: This command is different than the <b>GAUSS compile</b> command, which compiles a program and saves the pseudocode as a file.</i>
<b>Edit Main File</b>	Opens the specified main file in an edit window.
<b>Debug Main File</b>	Runs the main file in the debugger.

### 4.1.12 Working Directory Toolbar

You can use the Working Directory toolbar to quickly change your working directory.




Figure 4.3: Working Directory Toolbar

<b>Current Working Directory List</b>	Displays the name of the current working directory and lets you quickly change the working directory to one of the directories listed.
<b>Change Working Directory</b>	Browses to a new directory.

### 4.1.13 Debug Toolbar

You can use the Debug toolbar for quick access to commands while debugging a file.




Figure 4.4: Debug Toolbar

<b>Go</b>	Starts the debugger.
<b>Stop</b>	Stops the debugger.
<b>Toggle Breakpoint</b>	Enables or disables a breakpoint at the cursor in the active file.
<b>Clear All Breakpoints</b>	Removes all line and procedure breakpoints from the active file.
<b>Set Watch</b>	Opens the Matrix Editor for watching changing variable data. For more information about viewing variables see <a href="#">VIEWING VARIABLES, Section 5.5.5</a> .
<b>Step Into</b>	Runs the next executable line of code in the application and steps into procedures.

<b>Step Over</b>	Runs the next executable line of code in the application but does not step into procedures.
<b>Step Out</b>	Runs the remainder of the current procedure and stops at the next line in the calling procedure. Step Out returns if a breakpoint is encountered.
<b>Run to Cursor</b>	Runs the program until it reaches the cursor position.

### 4.1.14 Window Toolbar

You can use the Window toolbar for quick access to window commands.




Figure 4.5: Window Toolbar

<b>Activate Cmd Window</b>	Makes the Command window the active window.
<b>Activate/Deactivate Output Window</b>	Splits the output from the Command Input-Output window, or deactivates Output window.
<b>Activate Debug Window</b>	Makes the Debug window the active window.
<b>Source/Symbol View</b>	Displays or undisplay the Source/Symbol window.
<b>Error Output</b>	Opens or closes the Error Output window.

**Window**

<b>Tile windows horizontally</b>	Tiles the active window and the Output or Command Input - Output window horizontally.
<b>Tile windows vertically</b>	Tiles the active window and the Output or Command Input - Output window vertically.
<b>Src Browser replaces window with new file contents</b>	If selected, the next file browsed in the Source Browser will be displayed in the same window.

**4.1.15 Status Bar**

The status bar is located along the bottom of the **GAUSS** window. The status of the windows and processes are shown on the status bar.

**4.1.16 GAUSS Status**

The first section of the status bar shows the current **GAUSS** status. From time to time you are alerted to the task **GAUSS** is performing by new messages appearing in the status bar.




Figure 4.6: Status Bar

<b>Cursor Location</b>	The line number and column number where the cursor is located appear on the status bar for the active window. When a block of text is selected, the values indicate the first position of the selected text.
<b>DATALOOP</b>	DATALOOP appears on the status bar to indicate the Dataloop Translator is turned on.

<b>OVR</b>	OVR appears on the status bar when typing replaces the existing text with text you enter. When OVR does not appear on the status bar, typing inserts text without deleting the existing text. Press the INSERT key to toggle between the two conditions.
<b>CAP</b>	CAP appears on the status bar to indicate the Caps Lock key has been pressed and all text you enter will appear in upper case.
<b>NUM</b>	NUM appears on the status bar to indicate the Num Lock key has been pressed and the keypad numbers are active.

# Using the Windows Interface 5

The **GAUSS** graphical user interface is a multiple document interface. The interface consists of edit windows and the Command Input - Output window. Integrated into **GAUSS** is a full debugger with breakpoints and watch variables. The **GAUSS** graphical user interface also incorporates the Matrix Editor (see Chapter 6), Library Tool (see Chapter 7), and GAUSS Source Browser (see Chapter 8), as well as a context-sensitive HTML Help system (see Chapter 9).

## 5.1 Using the GAUSS Edit Windows

The **GAUSS** edit windows provide syntax color coding and auto-formatting as well as easy access to the Matrix Editor and Library Tool, and include an integrated context-sensitive help system accessible through the F1 key.

The edit windows provide standard text editing features like drag and drop text editing, and find and replace. The editor also lets you set bookmarks, define keystroke macros, find and replace using regular expressions, and run selected text from the editor.

### 5.1.1 Editing Programs

To begin editing, open an edit window by browsing to the source file, or by typing **edit** and the filename in the Command Input - Output window. If more than one file is open, the last file opened or run becomes the active window.

### 5.1.2 Using Bookmarks

Bookmarks are efficient placeholders used to identify particular sections or lines of code. To add or remove bookmarks, place the cursor in the line you want to bookmark and then press CTRL+F2, or click Toggle Bookmark on the Edit menu. You can jump to the next bookmark by pressing F2, or go to the previous bookmark by pressing SHIFT+F2.

To edit a list of all currently defined bookmarks, click Edit Bookmarks on the Edit menu. The Edit Bookmarks window allows you to add, remove, name or select the bookmark to which you wish to jump.

### 5.1.3 Changing the Editor Properties

You can customize the formatting of your code and text by changing font colors, fonts, adding line indentations, and adding line numbering to your programs. To access these properties, on the Configure menu click Editor Properties, or right-click on an edit window and click Properties on the context menu. For more information about the Editor Properties see EDITOR PROPERTIES, Section 5.6.2.

### 5.1.4 Using Keystroke Macros

**GAUSS** will save up to 10 separate keystroke macros.

To record a keystroke macro, press CTRL+SHIFT+R, or click Record Macro on the Edit menu. When you start recording the macro, a stop button will appear in the **GAUSS** window.



You create a macro by clicking Record Macro and pressing the keystrokes you want recorded. Once you have completed recording the macro, you can stop recording with the stop button. Once you have finished recording the macro, you can select one of ten macro names for it.

Use the following guidelines when creating and using your macro:

- Only keystrokes in the active window are recorded, not keystrokes in a dialog box.
- Only keystrokes are recorded, not mouse movements.

Macros are not saved when you close **GAUSS**.

If your macro is lengthy, consider creating a separate file and copying the information from the file into the active window, rather than using a macro to enter the information.

### 5.1.5 Using Margin Functions

The margin of the edit window can be used to show currently set bookmarks, currently set breakpoints, and line numbers. You can also select an entire line of text with a single click in the Selection Margin.

You can turn on or off the margin in the Misc tab of the Editor Properties dialog box.

### 5.1.6 Editing with Split Views

Using split views, you can edit two parts of the same program in the same buffer. To open split views, click Split Horizontally or Split Vertically on the Window menu.

### 5.1.7 Finding and Replacing Text

Along with a standard find and replace function, you can use the edit window to find and replace regular expressions. To find regular expressions, open the Find dialog box and select the checkbox for regular expressions.

### 5.1.8 Running Selected Text

There are three ways you can run selected text. First, highlight the text you want to run, then either press CTRL+R, drag and drop the selected text into the Command Input - Output window, or click “Run Selected Text” on the Run menu.

## 5.2 Using The Command Input - Output Window

The Command Input - Output window lets you input interactive commands and view the results. The Command Input - Output window can be split into two separate windows, one for input and one for output, by clicking Output Window on the Window menu.

Output will be written at the insertion point in the Command Input - Output window or the Output window, when it is a separate window. **GAUSS** commands cannot be executed from this window.

From the Command Input - Output window, you can run saved programs. You can view or edit the data of any variable in the active workspace with the Matrix Editor. You can also open files for editing or to debug.

The **GAUSS** Command Input - Output window has many of the same features that the **GAUSS** text editor has. You can cut and paste text. You can search the buffer of the Command Input - Output window. You can also save the contents of the Command Input - Output window to a text file.

### 5.2.1 Running Commands

The **GAUSS** interface allows you to run programs that consist of single commands or blocks of commands executed interactively, as well as large-scale programs that may consist of commands in one or more files. The file that is run to execute the command is the main file (the file name displayed in the Main File list).

When you run commands interactively, the actual code being processed is called the “active block.” The active block is all code between the **GAUSS** prompt (>>) and the end of the current line. Thus, the active block can be one or more lines of code.

Interactive commands can be entered at the “>>” prompt in the Command Input - Output window or selected using the mouse and clicking the Run Selected Text button on the Main toolbar.

A block of code can be executed by selecting the block with the mouse and then running that block using the Run Selected Text function.

*Note: The **GAUSS** prompt (>>) at the beginning of the selected text is ignored.*

You can enter multi-line commands into the Command Input - Output window by pressing CTRL+ENTER at the end of each line. At the end of the final line in a multi-line command, press ENTER. The Command Input - Output window will automatically place a semicolon at the end of a single-line command before it is interpreted. For multi-line commands, you must enter a semicolon at the end of each line.

You can also run multi-line commands by pasting the text of a file at the **GAUSS** prompt, or selecting multiple lines of code from the Command Input - Output window and pressing CTRL+R.

You can repeat any of the last 20 lines entered into the command buffer by pressing CTRL+L to cycle through the last command buffer.

### 5.2.2 Running Programs in Files

You can execute the active file by clicking Run Active File on the Run menu, or by clicking the Run Currently Active File button on the Main toolbar.

You can execute the file displayed in the Main File list (the main file) by clicking Run Main file on the Run menu, or by clicking the Run Main File button on the Main toolbar.

## 5.3 Using Source View

Source View is a dockable dialog bar with two tabs that provide easy access to source files and symbols associated with your current **GAUSS** workspace.

### 5.3.1 Source Tab

The Source tab is a tree view that displays a list of active libraries and the source files they contain. Under each source file is a list of the symbols and procedures which they define. By using the right mouse button, you can search for symbols, open source files or view source file properties.

#### Opening a Source File

To open a source file, double click the file name or right click the file and click Edit.

#### Finding Commands in Source Files

To search the source files right click any file name in the source tab and click Find. In the Find dialog enter a keyword and click OK.

### 5.3.2 Symbols Tab

The Symbols tab contains a tree view of the **GAUSS** workspace global symbols organized by symbol type: Matrices, Arrays, Strings, String Arrays, and Structures.

#### Editing or Viewing a Symbol

To edit or view a symbol, double-clicking on it or right-clicking and selecting Edit from the menu.

#### Finding Symbols in Source Files

To search the source files right click any file name in the source tab and click Find. In the Find dialog enter a keyword and click OK.

## 5.4 Using the Error Output Window

The Error Output window allows error messages to be output to a separate window, instead of the **GAUSS** Input - Output window. When an error occurs, you can open the program or source file directly from the Error Output window.

To open the program or source file, press F4 or double click the error message. The file will open at the line the error occurred.

## 5.5 Using The Debugger

The debugger greatly simplifies program development. With all of the features of a dedicated debugging system, the debugger can help you to quickly identify and solve logic errors at run-time.

The debugger is integrated into the multiple document interface of **GAUSS**; it uses the interface tools, such as the edit windows, the Matrix Editor, and the Command Input - Output window for debugging. So while using the debugger, you still have all the features of the edit windows and Matrix Editor, along with **GAUSS**'s suite of debugging tools.

You use the debugger to watch the program code as it runs. Prior to running the debugger, breakpoints and watch variables can be set to stop the program at points you set and provide additional data as the code is run.

### 5.5.1 Starting and Stopping the Debugger

You can start the debugger by clicking Go on the Debug menu or the Debug toolbar.

When starting the debugger, you can choose to debug the active file or to debug the main file of a program. If you are debugging a single file and already have the file open, you can use the menu or toolbar to start the debugger on the file, or simply type **debug** and the filename in the Command Input - Output window.

When you start the debugger, the debugger automatically highlights the first line of code to be run. Any breakpoints are shown in the left margin of the window.

You can stop the debugger at any time by clicking Stop on the Debug menu or the Debug toolbar.

### 5.5.2 Using Breakpoints

Breakpoints stop code execution where you have inserted them. Breakpoints are normally set prior to running the debugger, but can also be set or cleared during debugging by clicking the Set/Clear Breakpoint command on the Debug menu.

The debugger supports two types of breakpoints: procedure breakpoints and line number breakpoints. Procedure breakpoints pause execution when the specified procedure or function is reached. Line number breakpoints pause execution when the specified line is reached. In either case, the break occurs before any of the **GAUSS** code for the procedure or line is executed. The debugger also allows you to specify a certain cycle of execution for a line number or procedure where you want the execution to be paused. The cycle count is for the occurrence of the line number or procedure, not the number of times a line is to be skipped.

### 5.5.3 Setting and Clearing Breakpoints

You can set or clear a line breakpoint in the highlighted line of code by clicking Set/Clear Breakpoint on the Debug menu or by pressing the F9 key.

To set breakpoints in any part of the file not currently being executed, just click the line where you want the breakpoint to be, then click Toggle Breakpoint.

To clear breakpoints in the file, click a line of code that has a breakpoint set and then click Set/Clear Breakpoint. You can also clear all breakpoints from the active file by clicking Clear All Breakpoints.

### Using the Breakpoint Editor to Set and Clear Breakpoints

The Breakpoint Editor allows you to set or clear both line and procedure breakpoints. It also lets you specify cycles of execution for breakpoints. With the Breakpoint Editor, you can set or clear breakpoints in any program currently in your working directory.

### 5.5.4 Stepping Through a Program

**GAUSS**'s debugger includes the ability to step into, step out of, and step over code during debugging.

Use Step Into to execute the line of code currently highlighted by the debugger.

Use Step Out to execute to the end of the current function without pause and return to the calling function.

Use Step Over to execute the line of code currently highlighted by the debugger without entering the functions that are called.

### 5.5.5 Viewing and Editing Variables

**GAUSS** allows you to view and edit the values of variables during debugging.

#### Viewing Variable Values During Debugging

Once the debugger is started, the editor window uses floatover variable windows for viewing variable data. Floatover variable windows give a quick view of the value a variable currently holds by simply moving your mouse over the variable name in the edit window.

The floatover variable window is only intended to give a quick view of the data, so it may not show all data held by the variable. If the variable data is incomplete, the floatover variable window will display an arrow to show that there is more data. If you need to view more data, open the Matrix Editor by highlighting the variable name and pressing CTRL+E.

#### Editing Variable Values During Debugging

The debugger integrates the Matrix Editor to edit values of loaded variables, or to use as a watch window to view the changing values of variables as you step through a program.

To edit a variable value, highlight the variable in the edit window, or the Command Input - Output window and then open the Matrix Editor. You can use the menu or toolbar to start the Matrix Editor, or simply type CTRL+E.

### **Making a Watch Window**

You can make the Matrix Editor a Watch window, allowing you to watch the changing value of a variable as the lines of the program are executed. You can activate the Watch window by clicking Set Watch on the Debug menu, or by highlighting a variable name in the debugger window and pressing CTRL+E.

You use a Watch window to see how variables change in value during debugging. Watch variables can be specified prior to running the debugger or during a debugging session.

The debugger searches for a watch variable using the following order:

1. A local variable within a currently active procedure.
2. A global variable.

A watch variable can be the name of a matrix, a scalar, a string array, or a string. For a matrix or a string array, the first element is displayed. If a matrix element is clicked, the Matrix Editor is loaded with the matrix. The matrix elements can be changed during the debugging session.

## **5.6 Customizing GAUSS**

### **5.6.1 Preferences Dialog Box**

The Preferences dialog box lets you specify how **GAUSS** operates. To open the Preferences dialog box, click Preferences... on the Configure menu. The changes you make in the Preferences dialog box remain set between sessions.



---

## Run Options

<b>Dataloop Translator</b>	Specifies whether or not <b>GAUSS</b> will translate data loops into procedures.
<b>Translate Line Number Tracking</b>	Specifies whether or not <b>GAUSS</b> will preserve the line numbers of data loops after being translated to procedures.
<b>Line Number Tracking</b>	Specifies whether or not <b>GAUSS</b> will preserve line numbers of a file being compiled for the interpreter.
<b>Sound at End of Job</b>	Determines whether or not a sound is played at the end of the execution of <b>GAUSS</b> code. The sound can be selected using the Select button and played using the Test button.  The default is OFF.

## Compile Options

The Compile tab contains options that let you control how **GAUSS** compiles a program before it is run.

<b>Autoload</b>	Specifies whether the autoloader will automatically resolve references in your code. If Autoload is off, you must define all symbols used in your program.
<b>Autodelete</b>	Use Autodelete in conjunction with Autoload to control the handling of references to unknown symbols.
<b>GAUSS Library</b>	Specifies whether the autoloader will use the standard <b>GAUSS</b> library in compiling your code.
<b>User Library</b>	Specifies whether the autoloader will use the User Libraries in compiling your code.
<b>Declare</b>	Specifies whether the <b>GAUSS</b> compiler will display declare warnings

<b>Warnings</b>	in the Command Input - Output window. For more information on declare warnings see USING .DEC FILES, Section <a href="#">17.3.1</a> .
<b>Compiler Trace</b>	Specifies whether you would like to trace the file compilation by file opening and closing, specific lines, or whether you would like to trace by local and global symbols.

### Cmd Window

The Cmd Window tab contains options that let you control how the **GAUSS** Command Window operates.

<b>Action on Enter</b>	Specifies whether pressing ENTER executes the current whole line always or only when the cursor is at the end of a line. Also, specifies whether placing a semi-colon at the end of a line causes <b>GAUSS</b> to enter multi-line mode.
<b>Performance</b>	Specifies whether or not output is buffered, and sets the buffer size in kilobytes.
<b>Cmd Prompt</b>	Specifies whether new <b>GAUSS</b> prompts are inserted at the current cursor location, appended to the text in the Command window, or relocated on the line following the cursor.
<b>Output</b>	Specifies whether output from a <b>GAUSS</b> program is inserted at the current cursor location, appended to the text in the Command window, or written over the text following the cursor.

### DOS Compatibility

The DOS Compatibility tab lets you control the appearance of the DOS Compatibility window.

<b>Change Font</b>	Specifies what font the DOS Compatibility window will use.
<b>Tab size</b>	Specifies the tab size in a DOS Compatibility window

---

<b>Stay on top of GAUSS</b>	Specifies whether the DOS Compatibility window will stay on top of GAUSS.
-----------------------------	---

## File

The File tab contains options that let you control how **GAUSS** auto-saves your work.

<b>Save file on Execute</b>	Specifies whether open files will automatically be saved when a file is run. If the file you are running is loaded, it will be saved prior to execution, regardless of how it is executed (Run file, command line, main file, or active file). All open editor files, including the active file, are saved before execution.
-----------------------------	--

*Note: New, unsaved documents are not automatically backed up until you save them, giving them a file name. After you save the new file, it will be automatically backed up with all other open files.*

<b>Autosave</b>	Specifies whether you want <b>GAUSS</b> to automatically save your files at a set interval of time.
-----------------	---

<b>Edit Window Properties</b>	Specifies the initial window size of opened files.
-------------------------------	--

## Misc

The Misc tab contains several general options to control **GAUSS**.

<b>Show Tip of the Day at startup</b>	Turns on/off the Tip of the Day at startup.
---------------------------------------	---

<b>Keep Help Window On Top of GAUSS</b>	Specifies whether the Help window always stays on top of <b>GAUSS</b> when opened.
---	--

<b>Set Initial Window Position</b>	Specifies initial position of the Help window.
------------------------------------	--

<b>Graphics Editor License</b>	If you have purchased the Graphics Editor, this is where you will enter or change the Graphics Editor license key.
--------------------------------	--

### 5.6.2 Editor Properties

You can customize the formatting of your code and text by changing font colors, fonts, adding line indentations, and adding line numbering to your programs. To access these properties, on the Configure menu click Editor Properties.

#### Color/Font

<b>Color</b>	Specifies the way syntax coloring works in the editor.
<b>Font</b>	Specifies what font the edit window will use.

#### Language/Tabs

<b>Auto Indentation Style</b>	Specifies how the autoindenter will indent your code.
<b>Tabs</b>	Specifies how many spaces a tab has.
<b>Language</b>	Specifies what syntax the <b>GAUSS</b> editor will recognize for syntax coloring.
<b>Fixup Text Case While Typing Language Keywords</b>	Specifies whether the editor will automatically change the case of <b>GAUSS</b> keywords when they use the wrong case.

#### Misc

<b>Smooth Scrolling</b>	Enables or disables smooth scrolling when the window is scrolled up/down by one line or left/right by one character.
<b>Show Left Margin</b>	Enables or disables the editor's margin. The margin is used for showing breakpoints, bookmarks, or line numbers.
<b>Line Tooltips on Scroll</b>	Shows the first line number on screen as a tooltip as you scroll up and down the file.

---

<b>Allow Drag and Drop</b>	Enables or disables drag and drop functionality.
<b>Allow Column Selection</b>	Lets you select and manipulate columns of text.
<b>Confine Caret to Text</b>	Tells the <b>GAUSS</b> editor to interpret carets as text only rather than as substitution symbols or text.
<b>Color Syntax Highlighting</b>	Toggles on or off color syntax highlighting.
<b>Show Horizontal Scrollbar</b>	Toggles on or off the horizontal scrollbar.
<b>Show Vertical Scrollbar</b>	Toggles on or off the vertical scrollbar.
<b>Allow Vertical Splitting</b>	Toggles on or off the ability to split editor panes vertically.
<b>Allow Horizontal Splitting</b>	Toggles on or off the ability to split editor panes horizontally.
<b>Line Numbering</b>	Specifies the style and starting digit for line numbering.
<b>Max Undoable Actions</b>	Sets the number of actions that you can undo.

## 5.7 Using GAUSS Keyboard Assignments

### 5.7.1 Cursor Movement Keys

UP ARROW	Up one line
DOWN ARROW	Down one line
LEFT ARROW	Left one character

RIGHT ARROW	Right one character
CTRL+LEFT ARROW	Left one word
CTRL+RIGHT ARROW	Right one word
HOME	Beginning of line
END	End of line
PAGE UP	Next screen up
PAGE DOWN	Next screen down
CTRL+PAGE UP	Scroll window right
CTRL+PAGE DOWN	Scroll window left
CTRL+HOME	Beginning of document
CTRL+END	End of document

### 5.7.2 Edit Keys

BACKSPACE	Delete character to left of cursor, or delete selected text
DEL	Delete character to right of cursor, or delete selected text
CTRL+INS or CTRL+C	Copy selected text to Windows clipboard
SHIFT+DEL or CTRL+X	Delete selected text and place it onto Windows clipboard
SHIFT+INS or CTRL+V	Paste text from Windows clipboard at the cursor position
CTRL+Z	Undo last editing action

### 5.7.3 Text Selection Keys

SHIFT+UP ARROW	Select one line of text up
SHIFT+DOWN ARROW	Select one line of text down
SHIFT+LEFT ARROW	Select one character to the left
SHIFT+RIGHT ARROW	Select one character to the right
SHIFT+CTRL+LEFT ARROW	Select one word to the left
SHIFT+CTRL+RIGHT ARROW	Select one word to the right
SHIFT+HOME	Select to beginning of the line
SHIFT+END	Select to end of the line
SHIFT+PAGE UP	Select up one screen
SHIFT+PAGE DOWN	Select down one screen
SHIFT+CTRL+HOME	Select text to beginning of document
SHIFT+CTRL+END	Select text to end of document

### 5.7.4 Command Keys

CTRL+A	Redo
CTRL+C	Copy selection to Windows clipboard
CTRL+D	Open Debug window
CTRL+E	Open Matrix Editor
CTRL+F	Find/Replace text
CTRL+G	Go to specified line number
CTRL+I	Insert <b>GAUSS</b> prompt

CTRL+L	Insert last
CTRL+N	Make next window active
CTRL+O	Open Output window
CTRL+P	Print current window, or selected text
CTRL+Q	Exit <b>GAUSS</b>
CTRL+R	Run selected text
CTRL+S	Save window to file
CTRL+W	Open Command window
CTRL+V	Paste contents of Windows clipboard
CTRL+X	Cut selection to Windows clipboard
CTRL+Z	Undo

### 5.7.5 Function Keys

F1	Open <b>GAUSS</b> Help system or context-sensitive Help
F2	Go to next bookmark
F3	Find again
F4	Go to next search item in Source Browser
F5	Run Main File
F6	Run Active File
F7	Edit Main File
F8	Step Into
F9	Set/Clear breakpoint



F10	Step Over
ALT+F4	Exit <b>GAUSS</b>
ALT+F5	Debug Main File
CTRL+F1	Searches the active libraries for the source code of a function.
CTRL+F2	Toggle bookmark
CTRL+F4	Close active window
CTRL+F5	Compile Main File
CTRL+F6	Compile Active File
CTRL+F10	Step Out
ESC	Unmark marked text

### 5.7.6 Menu Keys

ALT+C	Configure menu
ALT+D	Debug menu
ALT+E	Edit menu
ALT+F	File menu
ALT+H	Help menu
ALT+R	Run menu
ALT+T	Tools menu
ALT+W	Window menu
ALT+V	View menu



# Matrix Editor 6


## 6.1 Using the Matrix Editor

The Matrix Editor lets you view and edit matrix data in your current workspace. You can open the Matrix Editor from either the Command Input - Output window or a **GAUSS** edit window by highlighting a matrix variable name and typing CTRL+E. You can view multiple matrices at the same time by opening more than one Matrix Editor.

### 6.1.1 Editing Matrices

The Matrix Editor will allow you to format matrices in decimal, scientific, Hexadecimal, or as text characters.

Just like a spreadsheet, when using the Matrix Editor, you can use your keyboard's arrow keys to quickly move between matrix positions. To edit a scalar value, select a cell and press Enter. You can use the Home and End keys to move to the beginning or end of a scalar. When finished editing, press Enter again.



	1	2	3	4	5	6
1	-0.599027	-0.929655	0.115338	-1.757482	1.535888	-1.495725
2	-0.111480	-0.037702	0.204989	0.347593	-0.012819	-1.722755
3	0.178803	0.617784	-1.052247	0.705609	2.091645	-0.895426
4	0.767604	-0.203127	-0.631640	-1.350959	0.761351	-1.178030
5	0.117648	1.068945	1.764540	-0.606348	-1.480696	-1.086387
6	-0.052457	-0.764470	-0.190555	0.283396	-1.028075	1.581555
7	-0.899732	0.985289	0.119769	0.879613	0.229761	0.692722
8	-1.256108	-0.106485	0.064285	1.035368	1.406847	-0.184096
9	0.477675	2.175634	-1.774649	-0.621144	-0.021926	-1.215881
10	-1.800023	-1.239619	-0.358918	0.540553	0.251617	1.193660
11	1.189641	1.127013	0.095447	-0.311108	-1.384710	0.600211
12	1.533650	-0.606602	-0.836900	0.073142	0.809363	-1.788690
13	-0.009426	0.865253	-0.244213	1.428293	-0.079062	0.304848
14	-0.128827	-0.042080	-0.402811	-1.132260	1.145335	-1.236843
15	0.271311	-0.077436	-0.557608	-0.233865	-0.657546	1.540636
16	0.078979	0.063193	0.475045	1.391413	-0.426015	0.045088
17	-0.165351	0.520752	0.163359	0.451091	0.854254	1.409358
18	0.294404	-0.844052	0.592042	-0.414982	-0.299230	0.647507
19	-1.035333	0.301635	-0.578786	-1.692544	-0.591808	0.613205
20	0.880547	-0.558911	1.283090	0.586586	-0.536145	-0.694828
21	1.801590	0.299676	-1.396833	0.804763	1.356855	-1.051223
22	-0.636420	-1.795291	-1.242900	-0.119345	-0.020353	-0.789638
23	1.149421	0.670398	-0.443740	-0.529286	-0.454323	-0.351678
24	-1.712764	-0.917710	0.037024	-0.959819	0.177282	0.594274

Figure 6.1: Matrix Editor

### 6.1.2 Viewing Variables

All variables are treated as matrices in **GAUSS**. A scalar is simply a  $1 \times 1$  matrix. A vector is a  $(N \times 1)$  or  $(1 \times N)$  matrix. So you can use the Matrix Editor to view and monitor the value of any variable. You can update the value of a variable at any time by using the Reload function. When using the Matrix Editor to view, edit or monitor smaller matrices, you can minimize space it occupies on the screen by selecting Minimal View from the View menu.

By using the Auto-reload function, **GAUSS** will automatically update the values of variables in the Matrix Editor. Using Auto-reload you can create a watch window.

### Setting Watch Variables

Watch Variables allow you to see how variables change in value while debugging a program. A watch variable can be the name of a matrix, a scalar, an array, a string array, or a string.

The debugger searches for a watch variable in the following order:

- a local variable within a currently active procedure
- a global variable

### 6.1.3 Matrix Editor Menu Bar

#### Matrix Menu

The Matrix menu lets you control the data of the Matrix in the Matrix Editor as an entire set.

<b>Load</b>	Clears any existing grid and loads any named matrix from the <b>GAUSS</b> workspace to the grid.
<b>Reload</b>	Reloads the existing matrix with the name shown on the Title bar.

<b>Auto-Reload</b>	Automatically updates the data shown in the Matrix Editor, creating a watch window.
<b>Save</b>	Saves the grid as a matrix in the <b>GAUSS</b> workspace. If a matrix of the same name already exists in the workspace, it is overwritten.

### Format Menu

The Format menu lets you control the way the data is presented in the Matrix Editor.

<b>Decimal</b>	Display selected elements as decimal numbers.
<b>Scientific</b>	Display selected elements using scientific notation.
<b>Hexadecimal</b>	Display selected elements as hexadecimal numbers.
<b>Character</b>	Display selected elements as character data.
<b>Precision...</b>	Specify precision of selected elements.

### Edit Menu

The Edit menu gives you tools to control the data in the Matrix Editor.

<b>Clear All</b>	Clears the grid of all values but keep the row and column order.
<b>Preferences</b>	Sets several matrix options, including the number of digits to the right of the decimal point, cell height and width, and whether pressing the Enter key moves the cursor down or over one cell. These options, along with screen position and window state, are saved between sessions.

---

## View Menu

The View menu lets you control the Matrix Editor window. The View menu also lets you control your view of imaginary numbers.

<b>Dimension</b>	Specifies which two-dimensional subarray of an N-dimensional array to display by indexing the N-2 leading dimensions of the array.
<b>Real Parts</b>	Specifies that you want the real parts of imaginary numbers to be displayed in the Matrix Editor.
<b>Imaginary Parts</b>	Specifies that you want the imaginary parts of numbers to be displayed in the Matrix Editor.
<b>Minimal View</b>	Minimizes the amount of screen space occupied by the Matrix Editor. This is especially useful for creating watch windows for single variables.
<b>Stay on Top</b>	Forces the Matrix Editor window to remain visible on the screen even when the interface focus has shifted to another window.





# Library Tool 7

## 7.1 Using the Library Tool

The Library Tool lets you quickly manage your libraries. You can add and remove libraries and you can add and remove files within the libraries.

### 7.1.1 Managing Libraries

Using the New Library button, you can create a new library for organizing your code. You can remove a library by selecting the Delete Library button.

### 7.1.2 Managing the Library Index

To add absolute path names to the library index, use the Add Paths button. To only use file names for searching libraries, use the Strip Paths button. Use Rebuild to recompile all the files used in the library, and rebuild the library index file. Use the Revert to Original button to revert to the configuration the library was in when the Library Tool was opened.




Figure 7.1: Library Tool

---

### 7.1.3 Managing Library Files

You can add files to a library with the Add button. You can remove files from a library with the Remove button. After changing source files referred to in a library, select the files in the file list and update the library index with the Update button. To remove multiple files from a library, select the files in the file selection window, and use the Clear Selection button.

For more information about libraries, see [LIBRARIES](#), Chapter 17.



# GAUSS Source Browser 8

The **GAUSS** Source Browser lets users quickly find, view, and if necessary, modify source code. Both the TGAUSS and **GAUSS** Source Browsers can be used to search for external symbols in active libraries. The **GAUSS** Source Browser can also be used to search for symbols in any directory or source file.

## 8.1 Using the Source Browser in TGAUSS

To start the Source Browser in TGAUSS, type **BROWSE** followed by a symbol name. When the Source Browser is active, the prompt displays **Browse: . GAUSS** searches through all active libraries for the file in which the symbol is defined. If found, the file containing the source code is opened in the default editor.

Wildcard (\*) searches can also be used. When using wildcard searches, each symbol that the string matches will be displayed on-screen in a numbered list. To select a specific command to view in the default editor, select the number from the list.

The Source Browser will remain active until you type **CTRL-C** to return to the **GAUSS** prompt.

## 8.2 Using the Source Browser in GAUSS

To open the Source Browser in **GAUSS**, from the Tools menu select Source Browser.

Using the Source Browser you can search a file for a specified symbol or search across all the source files in a directory. Using a comma separated list of files and directories in the Look in: list, you can search multiple locations in a single search. When searching for symbols, you can use wildcards (\*) to further modify the scope of the search.

*Note: The Source Browser does not search recursively through sub-folders. To search sub-folders during a search, add the sub-folder names to the Look in: list.*

Once the search is complete, the Source Browser lists where the specified symbol was found. The Filename column of the Results List shows the file in which the symbol was found. The Line column shows the line number where symbol was found and the Line Description column shows the text of the line where the symbol was found.

Search locations typed into the Look in: text box will persist between Source Browser sessions.

<b>Pattern:</b>	Defines search pattern.
<b>Look in:</b>	Limits the scope of the search to specific files or directories. Using a comma separated list, searches multiple files and directories in a single search.
<b>Match Case</b>	Makes search case-sensitive.
<b>Match whole word</b>	Limits search to entire words.
<b>Stay on top</b>	Keeps the Source Browser on top even when another window is active.
<b>F4 Opens New Window</b>	Sets F4 to open new window.
<b>Browse</b>	Lets you limit the scope of the search to specific files or directories.
<b>Search</b>	Initiates search.
<b>Results List</b>	Lists occurrences of selected symbol in specified files or directories.




Figure 8.1: Source Browser

<b>Status</b>	Lists how many occurrences there were, and how many files the symbol occurred in.
<b>Close</b>	Closes the Source Browser.

### 8.2.1 Opening Files From the Source Browser

Double-click the file name to open a file in its own editor window. When opened, the cursor is placed at the beginning of the line selected in the Results List. By double-clicking different files in the Source Browser, you can open each file in its own separate editor window.

Use the F4 key to quickly view or edit the next file in the Results List using the active editor window. Using the F4 key opens the file in the active editor window and places the cursor at the beginning of the line in which the symbol was found. The F4 key uses the active editor window to display the source file; it will not open an editor window to display files. You can use the F4 key from either the Source Browser or from the active editor window to move to the next occurrence of the symbol shown in the Results List.

Use SHIFT+F4 to quickly view or edit the previous file in the Results List using the active editor window. Using the F4 key opens the file in the active editor window and places the cursor at the beginning of the line in which the symbol was found.

### 8.2.2 Source Browser Keyboard Controls

UP ARROW	Moves to the previous occurrence in the Results List.
DOWN ARROW	Moves to the next occurrence in the Results List.
HOME	Moves to the first occurrence in the Results List.
END	Moves to the last occurrence in the Results List.
F4	Shows the next occurrence in the active editor window.
SHIFT+F4	Shows the previous occurrence in the active editor window.
TAB	Moves to next field.
ENTER	Starts Search.



# GAUSS Help 9

## 9.1 Help Menu

From the Help menu, you can directly access the online **USER GUIDE**, Keyboard Assignments list, and **LANGUAGE REFERENCE**. Pressing F1 also accesses the Help system, displaying either the **INTRODUCTION** to the **USER GUIDE** or, if an object has focus and help can be directly accessed, help for that object.

## 9.2 Context-Sensitive Help

**GAUSS** integrates a context-sensitive Help system to help you use the **GAUSS** environment and the **GAUSS** language. Context-sensitive means that Help for the object with focus is displayed without navigating through the Help system. For example, to display Help on a keyword in the **GAUSS** language in a **GAUSS** edit window or the Command Input - Output window, place the insertion point on the keyword and press F1.

Several areas of the **GAUSS** interface are context-sensitive, including:

- **GAUSS** windows
- Toolbar buttons
- **GAUSS** menus
- The **GAUSS** language

For intrinsic commands and functions, the **GAUSS LANGUAGE REFERENCE** for the command is displayed. For other external procedures in active libraries, a window displays a source code file, allowing you to scroll to the desired symbol.

### 9.3 SHIFT+F1 Support

If you press SHIFT+F1 or click on the Help toolbar button (an arrow with a question mark), the pointer changes to a Help pointer (arrow + ?). Click on an object to display the Help system or, if available, context-sensitive Help for that object.

### 9.4 CTRL+F1 Support

You can search through all active libraries for any global symbol by placing the cursor on the symbol name and pressing CTRL+F1.

**GAUSS** searches through all active libraries for the file that the symbol is defined in. If found, the file containing the source code is opened in an edit window. If the file contains the code string `***> symbol_name` (without quotes) at the beginning of a line of commented code, the cursor will be placed at the beginning of that line. If the string is not found in the file, the cursor will be placed at the beginning of the file.

To properly implement this functionality in your own source code, place

`***> symbol_name`

at the beginning of a line in a comment block.

---

## 9.5 ToolTips

A ToolTip is a small label that is displayed when the mouse pointer is held over a **GAUSS** button. The ToolTip will give a brief description of the button's function.

## 9.6 Other Help

**GAUSS** includes full online versions of the **GAUSS LANGUAGE REFERENCE** and **GAUSS USER GUIDE** in PDF format. These manuals are available for download; contact Aptech Systems for download instructions.

The Gaussians mail list is an e-mail list providing users of **GAUSS** an easy way to reach other **GAUSS** users. Gaussians provides a forum for information exchange, tips and experiences using **GAUSS**. For more information about the Gaussians mail list, see the Resource Library page at <http://www.aptech.com>. You can also e-mail [support@aptech.com](mailto:support@aptech.com) when you have current Premier Support.



# Language Fundamentals 10

**GAUSS** is a compiled language. **GAUSS** is also an interpreter. A compiled language, because **GAUSS** scans the entire program once and translates it into a binary code before it starts to execute the program. An interpreter, because the binary code is not the native code of the CPU. When **GAUSS** executes the binary pseudocode it must “interpret” each instruction for the computer.

How can **GAUSS** be so fast if it is an interpreter? Two reasons. First, **GAUSS** has a fast interpreter, and the binary compiled code is compact and efficient. Second, and most significantly, **GAUSS** is a matrix language. It is designed to tackle problems that can be solved in terms of matrix or vector equations. Much of the time lost in interpreting the pseudocode is made up in the matrix or vector operations.

This chapter will enable you to understand the distinction between “compile time” and “execution time”, two very different stages in the life of a **GAUSS** program.

## 10.1 Expressions

An expression is a matrix, string, constant, function reference, procedure reference, or any combination of these joined by operators. An expression returns a result that can be assigned to a

variable with the assignment operator '='.

## 10.2 Statements

A statement is a complete expression or command. Statements end with a semicolon.

```
y = x*3;
```

If an expression has no assignment operator (=), it will be assumed to be an implicit **print** statement:

```
print x*3;
```

or

```
x*3;
```

Here is an example of a statement that is a command rather than an expression:

```
output on;
```

Commands cannot be used as a part of an expression.

There can be multiple statements on the same line as long as each statement is terminated with a semicolon.

### 10.2.1 Executable Statements

Executable statements are statements that can be “executed” over and over during the execution phase of a **GAUSS** program (execution time). As an executable statement is compiled, binary code is added to the program being compiled at the current location of the instruction pointer. This binary code will be executed whenever the interpreter passes through this section of the program. If this code is in a loop, it will be executed each iteration of the loop.

Here are some examples of executable statements:

```
y = 34.25;
```

```
print y;
```

```
x = 1 3 7 2 9 4 0 3 ;
```

### 10.2.2 Nonexecutable Statements

Nonexecutable statements are statements that have an effect only when the program is compiled (compile time). They generate no executable code at the current location of the instruction pointer.

Here are two examples:

```
declare matrix x = 1 2 3 4 ;
```

```
external matrix ybar;
```

Procedure definitions are nonexecutable. They do not generate executable code at the current location of the instruction pointer.

Here is an example:

```
zed = rndn(3,3);

proc sqrtinv(x);
    local y;
    y = sqrt(x);
    retp(y+inv(x));
endp;

zsi = sqrtinv(zed);
```

There are two executable statements in the example above: the first line and the last line. In the binary code that is generated, the last line will follow immediately after the first line. The last line is the **call** to the procedure. This generates executable code. The procedure definition generates no code at the current location of the instruction pointer.

There is code generated in the procedure definition, but it is isolated from the rest of the program. It is executable only within the scope of the procedure and can be reached only by calling the procedure.

## 10.3 Programs

A program is any set of statements that are run together at one time. There are two sections within a program.

### 10.3.1 Main Section

The main section of the program is all of the code that is compiled together **WITHOUT** relying on the autoloader. This means code that is in the main file or is included in the compilation of the main file with an **#include** statement. **ALL** executable code should be in the main section.

There must always be a main section even if it consists only of a call to the one and only procedure called in the program.



### 10.3.2 Secondary Sections

Secondary sections of the program are files that are neither run directly nor included in the main section with **#include** statements.

The secondary sections of the program can be left to the autoloader to locate and compile when they are needed. Secondary sections must have only procedure definitions and other nonexecutable statements.

**#include** statements are allowed in secondary sections as long as the file being included does not violate the above criteria.

Here is an example of a secondary section:

```
declare matrix tol = 1.0e-15;

proc feq(a,b);
    retp(abs(a-b) <= tol);
endp;
```

## 10.4 Compiler Directives

Compiler directives are commands that tell **GAUSS** how to process a program during compilation. Directives determine what the final compiled form of a program will be. They can affect part or all of the source code for a program. Directives are not executable statements and have no effect at run-time.

The **#include** statement mentioned earlier is actually a compiler directive. It tells **GAUSS** to compile code from a separate file as though it were actually part of the file being compiled. This code is compiled in at the position of the **#include** statement.

Here are the compiler directives available in **GAUSS**:

<b>#define</b>	Define a case-insensitive text-replacement or flag variable.
----------------	--

<b>#definecs</b>	Define a case-sensitive text-replacement or flag variable.
<b>#undef</b>	Undefine a text-replacement or flag variable.
<b>#ifdef</b>	Compile code block if a variable has been <b>#define</b> 'd.
<b>#ifndef</b>	Compile code block if a variable has not been <b>#define</b> 'd.
<b>#iflight</b>	Compile code block if running <b>GAUSS Light</b> .
<b>#ifdos</b>	Compile code block if running DOS.
<b>#ifos2win</b>	Compile code block if running OS/2 or Windows.
<b>#ifunix</b>	Compile code block if running UNIX.
<b>#else</b>	Else clause for <b>#if-#else-#endif</b> code block.
<b>#endif</b>	End of <b>#if-#else-#endif</b> code block.
<b>#include</b>	Include code from another file in program.
<b>#lineson</b>	Compile program with line number and file name records.
<b>#linesoff</b>	Compile program without line number and file name records.
<b>#srcfile</b>	Insert source file name record at this point (currently used when doing data loop translation).
<b>#srcline</b>	Insert source file line number record at this point (currently used when doing data loop translation).

The **#define** statement can be used to define abstract constants. For example, you could define the default graphics page size as:

```
#define hpage      9.0
#define vpage      6.855
```

and then write your program using **hpage** and **vpage**. **GAUSS** will replace them with 9.0 and 6.855 when it compiles the program. This makes a program much more readable.

The **#ifdef**–**#else**–**#endif** directives allow you to conditionally compile sections of a program, depending on whether a particular flag variable has been **#define**'d. For example:

```
#ifdef log_10
    y = log(x);
#else
    y = ln(x);
#endif
```

This allows the same program to calculate answers using different base logarithms, depending on whether or not the program has a **#define log\_10** statement at the top.

**#undef** allows you to undefine text-replacement or flag variables so they no longer affect a program, or so you can **#define** them again with a different value for a different section of the program. If you use **#definecs** to define a case-sensitive variable, you must use the right case when **#undef**'ing it.

With **#lineson**, **#linesoff**, **#srcline**, and **#srcfile** you can include line number and file name records in your compiled code, so that run-time errors will be easier to track down. **#srcline** and **#srcfile** are currently used by **GAUSS** when doing data loop translation.

For more information on line number tracking, see **DEBUGGING**, Section 18.3 and see **DEBUGGING DATA LOOPS**, Section 21.3. See also **#lineson** in the **GAUSS LANGUAGE REFERENCE**.

The syntax for **#srcfile** and **#srcline** is different than for the other directives that take arguments. Typically, directives do not take arguments in parentheses; that is, they look like keywords:

```
#define red 4
```

**#srcfile** and **#srcline**, however, do take their arguments in parentheses (like procedures):

```
#srcline(12)
```

This allows you to place **#srcline** statements in the middle of **GAUSS** commands, so that line numbers are reported precisely as you want them. For example:

```
#srcline(1) print "Here is a multi-line "  
#srcline(2) "sentence--if it contains a run-time error, "  
#srcline(3) "you will know exactly "  
#srcline(4) "which part of the sentence has the problem.";
```

The argument supplied to **#srcfile** does not need quotes:

```
#srcfile(/gauss/test.e)
```

## 10.5 Procedures

A procedure allows you to define a new function which you can then use as if it were an intrinsic function. It is called in the same way as an intrinsic function.

```
y = myproc(a,b,c);
```

Procedures are isolated from the rest of your program and cannot be entered except by calling them. Some or all of the variables inside a procedure can be **local** variables. **local** variables exist only when the procedure is actually executing and then disappear. Local variables cannot get mixed up with other variables of the same name in your main program or in other procedures.

For details on defining and calling procedures, see PROCEDURES AND KEYWORDS, chapter 12.

## 10.6 Data Types

There are four basic data types in **GAUSS**, matrices, N-dimensional arrays, strings and string arrays. It is not necessary to declare the type of a variable, but it is good programming practice to respect the types of variables whenever possible. The data type and size can change in the course of a program.

The **declare** statement, used for compile-time initialization, enforces type checking.

Short strings of up to 8 bytes can be entered into elements of matrices, to form character matrices (For details, see **CHARACTER MATRICES**, Section [10.6.6](#)).

### 10.6.1 Constants

The following constant types are supported:

#### Decimal

Decimal constants can be either integer or floating point values:

1.34e-10

1.34e123

-1.34e+10

-1.34d-10

1.34d10

1.34d+10

123.456789345

Up to 18 consecutive digits before and after the decimal point (depending on the platform) are significant, but the final result will be rounded to double precision if necessary. The range is the same as for matrices (For details, see [MATRICES](#), Section [10.6.2](#)).

### String

String constants are enclosed in quotation marks:

“This is a string.”

### Hexadecimal Integer

Hexadecimal integer constants are prefixed with **0x**:

0x0ab53def2

### Hexadecimal Floating Point

Hexadecimal floating point constants are prefixed with **0v**. This allows you to input a double precision value exactly as you want using 16 hexadecimal digits. The highest order byte is to the left:

0vfff8000000000000

10.6.2 Matrices

Matrices are 2-dimensional arrays of double precision numbers. All matrices are implicitly complex, although if it consists only of zeros, the imaginary part may take up no space. Matrices are stored in row major order. A 2×3 real matrix will be stored in the following way from the lowest addressed element to the highest addressed element:

[1, 1] [1, 2] [1, 3] [2, 1] [2, 2] [2, 3]

A 2×3 complex matrix will be stored in the following way from the lowest addressed element to the highest addressed element:

(*real part*) [1, 1] [1, 2] [1, 3] [2, 1] [2, 2] [2, 3]  
(*imaginary part*) [1, 1] [1, 2] [1, 3] [2, 1] [2, 2] [2, 3]

Conversion between complex and real matrices occurs automatically and is transparent to the user in most cases. Functions are provided to provide explicit control when necessary.

All elements of a **GAUSS** matrix are stored in double precision floating point format, and each takes up 8 bytes of memory. This is the IEEE 754 format:

Bytes	Data Type	Significant Digits	Range
8	floating point	15–16	$4.19 \times 10^{-307} \leq  X  \leq 1.67 \times 10^{+308}$

Matrices with only one element (1×1 matrices) are referred to as scalars, and matrices with only one row or column (1×N or N×1 matrices) are referred to as vectors.

Any matrix or vector can be indexed with two indices. Vectors can be indexed with one index. Scalars can be indexed with one or two indices also, because scalars, vectors, and matrices are the same data type to **GAUSS**

The majority of functions and operators in **GAUSS** take matrices as arguments. The following functions and operators are used for defining, saving, and loading matrices:

[ ]	Indexing matrices.
=	Assignment operator.
	Vertical concatenation.
~	Horizontal concatenation.
<b>con</b>	Numeric input from keyboard.
<b>cons</b>	Character input from keyboard.
<b>declare</b>	Compile-time matrix or string initialization.
<b>let</b>	Matrix definition statement.
<b>load</b>	Load matrix (same as <b>loadm</b> ).
<b>readr</b>	Read from a <b>GAUSS</b> matrix or data set file.
<b>save</b>	Save matrices, procedures and strings to disk.
<b>saved</b>	Convert a matrix to a <b>GAUSS</b> data set.
<b>stof</b>	Convert string to matrix.
<b>submat</b>	Extract a submatrix.
<b>writer</b>	Write data to a <b>GAUSS</b> data set.

Following are some examples of matrix definition statements.

An assignment statement followed by data enclosed in braces is an implicit **let** statement. Only constants are allowed in **let** statements; operators are illegal. When braces are used in **let** statements, commas are used to separate rows. The statement

```
let x = 1 2 3, 4 5 6, 7 8 9 ;
```

or



```
x = 1 2 3, 4 5 6, 7 8 9 ;
```

will result in

```
x = 1 2 3
    4 5 6
    7 8 9
```

The statement

```
let x[3,3] = 1 2 3 4 5 6 7 8 9;
```

will result in

```
x = 1 2 3
    4 5 6
    7 8 9
```

The statement

```
let x[3,3] = 1;
```

will result in

```
x = 1 1 1
    1 1 1
    1 1 1
```

The statement

```
let x[3,3];
```

will result in

$$x = \begin{bmatrix} 0 & 0 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & 0 \end{bmatrix}$$

The statement

```
let x = 1 2 3 4 5 6 7 8 9;
```

will result in

$$x = \begin{bmatrix} 1 \\ 2 \\ 3 \\ 4 \\ 5 \\ 6 \\ 7 \\ 8 \\ 9 \end{bmatrix}$$

Complex constants can be entered in a **let** statement. In the following example, the + or - is not a mathematical operator, but connects the two parts of a complex number. There should be no spaces between the + or - and the parts of the number. If a number has both real and imaginary parts, the trailing 'i' is not necessary. If a number has no real part, you can indicate that it is imaginary by appending the 'i'. The statement

```
let x[2,2] = 1+2i 3-4 5 6i;
```

will result in

$$x = \begin{bmatrix} 1 + 2i & 3 - 4i \\ 5 & 0 + 6i \end{bmatrix}$$

Complex constants can also be used with the **declare**, **con** and **stof** statements.

An “empty matrix” is a matrix that contains no data. Empty matrices are created with the **let** statement and braces:

```
x = {};
```

Empty matrices are supported by several functions, including **rows** and **cols** and the concatenation ( $\sim$ ,  $|$ ) operators.

```
x = {};  
hsec0 = hsec;  
do until hsec-hsec0 > 6000;  
    x = x ~ data_in(hsec-hsec0);  
endo;
```

You can test whether a matrix is empty by entering **rows**( $x$ ), **cols**( $x$ ) and **scalerr**( $x$ ). If the matrix is empty **rows** and **cols** will return a 0, and **scalerr** will return 65535.

The  $\sim$  is the horizontal concatenation operator and the  $|$  is the vertical concatenation operator. The statement

```
y = 1~2|3~4;
```

will be evaluated as

```
y = (1 ~ 2) | (3 ~ 4);
```

and will result in a 2×2 matrix because horizontal concatenation has precedence over vertical concatenation:

```
1  2  
3  4
```

The statement

```
y = 1+1~2*2|3-2~6/2;
```

will be evaluated as

```
y = ((1 + 1) ~ (2 * 2)) | ((3 - 2) ~ (6/2));
```

and will result in a 2×2 matrix because the arithmetic operators have precedence over concatenation:

```
2 4  
1 3
```

For more information, see **OPERATOR PRECEDENCE**, Section [11.7](#).

The **let** command is used to initialize matrices with constant values:

```
let x[2,2] = 1 2 3 4;
```

Unlike the concatenation operators, it cannot be used to define matrices in terms of expressions such as

```
y = x1-x2~x2|x3*3~x4;
```

The statement

```
y = x[1:3,5:8];
```

will put the intersection of the first three rows and the fifth through eighth columns of **x** into the matrix **y**.

The statement

```
y = x[1 3 1,5 5 9];
```

will create a 3×3 matrix **y** with the intersection of the specified rows and columns pulled from **x** (in the indicated order).

The following code

```
let r = 1 3 1; let c = 5 5 9; y = x[r,c];
```

will have the same effect as the previous example, but is more general.

The statement

```
y[2,4] = 3;
```

will set the 2,4 element of the existing matrix **y** to 3. This statement is illegal if **y** does not have at least 2 rows and 4 columns.

The statement

```
x = con(3,2);
```

will cause the following prompt to be printed in the window:

```
- (1,1)
```

indicating that the user should enter the [1,1] element of the matrix. Entering a number and then pressing ENTER will cause a prompt for the next element of the matrix to appear. Pressing ? will display a help screen, and pressing **x** will exit.

The statement

```
load x[] = b:mydata.asc
```

will load data contained in an ASCII file into an  $N \times 1$  vector **x**. (Use **rows(x)** to find out how many numbers were loaded, and use **reshape(x,N,K)** to reshape it to an  $N \times K$  matrix).

The statement

```
load x;
```

will load the matrix **x.fmt** from disk (using the current load path) into the matrix **x** in memory.

The statement

```
open d1 = dat1;  
x = readr(d1,100);
```

will read the first 100 rows of the **GAUSS** data set **dat1.dat**.

### 10.6.3 N-dimensional Arrays

Many **GAUSS** commands support arrays of  $N$  dimensions. The following commands may be used to create and manipulate an  $N$ -dimensional array:

<b>aconcat</b>	Concatenate conformable matrices and arrays in a user-specified dimension.
----------------	--

---

<b>aeye</b>	Create an N-dimensional array in which the planes described by the two trailing dimensions of the array are equal to the identity.
<b>areshape</b>	Reshape a scalar, matrix, or array into an array of user-specified size.
<b>arrayalloc</b>	Create an N-dimensional array with unspecified contents.
<b>arrayinit</b>	Create an N-dimensional array with a specified fill value.
<b>mattoarray</b>	Convert a matrix to a type array.

See N-DIMENSIONAL ARRAYS, Chapter 15, for a more detailed explanation.

## 10.6.4 Strings

Strings can be used to store the names of files to be opened, messages to be printed, entire files, or whatever else you might need. Any byte value is legal in a string from 0–255. The buffer where a string is stored always contains a terminating byte of ASCII 0. This allows passing strings as arguments to C functions through the Foreign Language Interface.

Here is a partial list of the functions for manipulating strings:

<b>\$+</b>	Combine two strings into one long string.
<b>^</b>	Interpret following name as a variable, not a literal.
<b>chrs</b>	Convert vector of ASCII codes to character string.
<b>dttostr</b>	Convert a matrix containing dates in DT scalar format to a string array.
<b>ftocv</b>	Character representation of numbers in N×K matrix.
<b>ftos</b>	Character representation of numbers in 1×1 matrix.
<b>ftostrC</b>	Convert a matrix to a string array using a C language format specification.

<b>getf</b>	Load ASCII or binary file into string.
<b>indcv</b>	Find index of element in character vector.
<b>lower</b>	Convert to lowercase.
<b>stof</b>	Convert string to floating point.
<b>strindx</b>	Find index of a string within a second string.
<b>strlen</b>	Length of a string.
<b>strsect</b>	Extract substring of string.
<b>strsplit</b>	Split an N×1 string vector into an N×K string array of the individual tokens.
<b>strsplitPad</b>	Split a string vector into a string array of the individual tokens. Pads on the right with null strings.
<b>strtodt</b>	Convert a string array of dates to a matrix in DT scalar format.
<b>strtof</b>	Convert a string array to a numeric matrix.
<b>strtofcplx</b>	Convert a string array to a complex numeric matrix.
<b>upper</b>	Convert to uppercase.
<b>vals</b>	Convert from string to numeric vector of ASCII codes.

Strings can be created like this:

```
x = "example string";
```

or

```
x = cons;                                /* keyboard input */
```

or



```
x = getf("myfile",0);      /* read a file into a string */
```

They can be printed like this:

```
print x;
```

A character matrix must have a '\$' prefixed to it in a **print** statement:

```
print $x;
```

A string can be saved to disk with the **save** command in a file with a .fst extension and then loaded with the **load** command:

```
save x;  
loads x;
```

or

```
loads x=x.fst;
```

The backslash is used as the escape character inside double quotes to enter special characters:

"\b"	backspace (ASCII 8)
"\e"	escape (ASCII 27)
"\f"	formfeed (ASCII 12)
"\g"	beep (ASCII 7)
"\l"	line feed (ASCII 10)
"\r"	carriage return (ASCII 13)
"\t"	tab (ASCII 9)
"\""	a backslash
"\###"	the ASCII character whose decimal value is "###".

When entering DOS pathnames in double quotes, two backslashes must be used to insert one backslash:

```
st = "c:\\gauss\\myprog.prg";
```

An important use of strings and character elements of matrices is with the substitution operator (^).

In the command

```
create f1 = olsdat with x,4,2;
```

by default, **GAUSS** will interpret the **olsdat** as a literal; that is, the literal name of the **GAUSS** data file you want to create. It will also interpret the **x** as the literal prefix string for the variable names: **x1 x2 x3 x4**.

If you want to get the data set name from a string variable, the substitution operator (^) could be used as:

```
dataset="olsdat";  
create f1=^dataset with x,4,2;
```

If you want to get the data set name from a string variable and the variable names from a character vector, use

```
dataset="olsdat";  
let vnames=age pay sex;  
create f1=^dataset with ^vnames,0,2;
```

The substitution operator (^) works with **load** and **save** also:

```
lpath="/gauss/procs";  
name="mydata";  
load path=^lpath x=^name;  
command="dir *.fmt";
```

The general syntax is:

*^variable\_name*

Expressions are not allowed. The following commands are supported with the substitution operator (^):

```
create f1=^dataset with ^vnames,0,2;
create f1=^dataset using ^cmdfile;
open f1=^dataset;
output file=^outfile;
load x=^datafile;
load path=^lpath x,y,z,t,w;
loadexe buf=^exefile;
save ^name=x;
save path=^spath;
dos ^cmdstr;
run ^prog;
msym ^mstring;
```

### 10.6.5 String Arrays

String arrays are  $N \times K$  matrices of strings. Here is a partial list of the functions for manipulating string arrays:

<b>\$ </b>	Vertical string array concatenation operator.
<b>\$~</b>	Horizontal string array concatenation operator.
<b>[ ]</b>	Extract subarrays or individual strings from their corresponding array, or assign their values.
<b>'</b>	Transpose operator.

<b>./</b>	Bookkeeping transpose operator.
<b>declare</b>	Initialize variables at compile time.
<b>delete</b>	Delete specified global symbols.
<b>fgetsa</b>	Read multiple lines of text from a file.
<b>fgetsat</b>	Reads multiple lines of text from a file, discarding newlines.
<b>format</b>	Define output format for matrices, string arrays, and strings.
<b>fputs</b>	Write strings to a file.
<b>fputst</b>	Write strings to a file, appending newlines.
<b>let</b>	Initialize matrices, strings, and string arrays.
<b>loads</b>	Load a string or string array file ( <b>.fst</b> file).
<b>lprint</b>	Print expressions to the printer.
<b>lshow</b>	Print global symbol table to the printer.
<b>print</b>	Print expressions on window and/or auxiliary output.
<b>reshape</b>	Reshape a matrix or string array to new dimensions.
<b>save</b>	Save matrix, string array, string, procedure, function or keyword to disk and gives the disk file either a <b>.fmt</b> , <b>.fst</b> or <b>.fcg</b> extension.
<b>show</b>	Display global symbol table.
<b>sortcc</b>	Quick-sort rows of matrix or string array based on character column.
<b>type</b>	Indicate whether variable passed as argument is matrix, string, or string array.
<b>typecv</b>	Indicate whether variables named in argument are strings, string arrays, matrices, procedures, functions or keywords.
<b>varget</b>	Access the global variable named by a string array.

---

<b>varput</b>	Assign the global variable named by a string array.
<b>vec</b>	Stack columns of a matrix or string array to form a column vector.
<b>vecr</b>	Stack rows of a matrix or string array to form a column vector.

String arrays are created through the use of the string array concatenation operators. Below is a contrast of the horizontal string and horizontal string array concatenation operators.

```
x = "age";  
y = "pay";  
n = "sex";  
s = x $+ y $+ n;  
sa = x $~ y $~ n;
```

```
s = agepaysex
```

```
sa = age    pay    sex
```

### 10.6.6 Character Matrices

Matrices can have either numeric or character elements. For convenience, a matrix containing character elements is referred to as a character matrix.

A character matrix is not a separate data type, but gives you the ability to store and manipulate data elements that are composed of ASCII characters as well as floating point numbers. For example, you may want to concatenate a column vector containing the names of the variables in an analysis onto a matrix containing the coefficients, standard errors, t-statistic, and p-value. You can then print out the entire matrix with a separate format for each column with one call to the function **printfm**.

The logic of the programs will dictate the type of data assigned to a matrix, and the increased flexibility allowed by being able to bundle both types of data together in a single matrix can be

very powerful. You could, for instance, create a moment matrix from your data, concatenate a new row onto it containing the names of the variables and save it to disk with the **save** command.

Numeric matrices are double precision, which means that each element is stored in 8 bytes. A character matrix can thus have elements of up to 8 characters.

**GAUSS** does not automatically keep track of whether a matrix contains character or numeric information. The ASCII to **GAUSS** conversion program ATOG will record the types of variables in a data set when it creates it. The **create** command will, also. The function **vartypef** gets a vector of variable type information from a data set. This vector of ones and zeros can be used by **printfm** when printing your data. Since **GAUSS** does not know whether a matrix has character or numeric information, it is up to you to specify which type of data it contains when printing the contents of the matrix. (For details, see **print** and **printfm** in the GAUSS LANGUAGE REFERENCE.)

Most functions that take a string argument will take an element of a character matrix also, interpreting it as a string of up to 8 characters.

### 10.6.7 Date and Time Formats

#### DT Scalar Format

The DT scalar format is a double precision representation of the date and time. In the DT scalar format, the number

20010421183207

represents 18:32:07 or 6:32:07 PM on April 21, 2001.

#### DTV Vector Format

The DTV vector is a 1×8 vector. The format for the DTV vector is:

- [1] Year
- [2] Month, 1-12
- [3] Day of month, 1-31
- [4] Hour of day, 0-23
- [5] Minute of hour, 0-59
- [6] Second of minute, 0-59
- [7] Day of week, 0-6 where 0 is Sunday
- [8] Day since beginning of year, 0-365

### UTC Scalar Format

The UTC scalar format is the number of seconds since January 1, 1970, Greenwich Mean Time.

### 10.6.8 Special Data Types

The IEEE floating point format has many encodings that have special meaning. The **print** command will print them accurately so that you can tell if your calculation is producing meaningful results.

#### NaN

There are many floating point encodings which do not correspond to a real number. These encodings are referred to as NaN's. NaN stands for Not A Number.

Certain numerical errors will cause the math coprocessor to create a NaN called an "indefinite". This will be printed as a -NaN when using the **print** command. These values are created by the following operations:

- $+\infty$  plus  $-\infty$
- $+\infty$  minus  $+\infty$
- $-\infty$  minus  $-\infty$

- $0 * \infty$
- $\infty / \infty$
- $0 / 0$
- Operations where one or both operands is a NaN
- Trigonometric functions involving  $\infty$

### INF

When the math coprocessor overflows, the result will be a properly signed infinity. Subsequent calculations will not deal well with an infinity; it usually signals an error in your program. The result of an operation involving an infinity is most often a NaN.

### DEN, UNN

When some math coprocessors underflow, they may do so gradually by shifting the significand of the number as necessary to keep the exponent in range. The result of this is a denormal (DEN). When denormals are used in calculations, they are usually handled automatically in an appropriate way. The result will either be an unnormal (UNN), which like the denormal represents a number very close to zero, or a normal, depending on how significant the effect of the denormal was in the calculation. In some cases the result will be a NaN.

Following are some procedures for dealing with these values. These procedures are not defined in the **Run-Time Library**. If you want to use them, you will need to define them yourself.

The procedure **is indef** will return 1 (true) if the matrix passed to it contains any NaN's that are the indefinite mentioned earlier. The **GAUSS** missing value code as well as **GAUSS** scalar error codes are NaN's, but this procedure tests only for indefinite:

```
proc is indef(x);  
    retp(not x $/= __INDEFn);  
endp;
```



Be sure to call **gausset** before calling **isindf**. **gausset** will initialize the value of the global **\_\_INDEFn** to a platform-specific encoding.

The procedure **normal** will return a matrix with all denormals and unnormals set to zero.

```
proc normal(x);
    retp(x .* (abs(x) .> 4.19e-307));
endp;
```

The procedure **isinf**, will return 1 (true) if the matrix passed to it contains any infinities:

```
proc isinf(x);
    local plus,minus;
    plus = __INFp;
    minus = __INFn;
    retp(not x /= plus or not x /= minus);
endp;
```

Be sure to call **gausset** before calling **isinf**. **gausset** will initialize the values of the globals **\_\_INFn** and **\_\_INFp** to platform specific encodings.

## 10.7 Operator Precedence

The order in which an expression is evaluated is determined by the precedence of the operators involved and the order in which they are used. For example, the **\*** and **/** operators have a higher precedence than the **+** and **-** operators. In expressions that contain these operators, the operand pairs associated with the **\*** or **/** operator are evaluated first. Whether **\*** or **/** is evaluated first depends on which comes first in the particular expression. For a listing of the precedence of all operators, see OPERATOR PRECEDENCE, Section 11.7.

The expression

$$-5+3/4+6*3$$

is evaluated as

$$(-5) + (3/4) + (6 * 3)$$

Within a term, operators of equal precedence are evaluated from left to right.

The term

$$2^3^7$$

is evaluated

$$(2^3)^7$$

In the expression

$$f1(x)*f2(y)$$

**f1** is evaluated before **f2**.

Here are some examples:

Expression	Evaluation
$a+b*c+d$	$(a + (b * c)) + d$
$-2+4-6*inv(8)/9$	$((-2) + 4) - ((6 * inv(8))/9)$
$3.14^5*6/(2+sqrt(3)/4)$	$((3.14^5) * 6)/(2 + (sqrt(3)/4))$
$-a+b*c^2$	$(-a) + (b * (c^2))$
$a+b-c+d-e$	$((((a + b) - c) + d) - e)$
$a^b^c*d$	$((a^b)^c) * d$
$a*b/d*c$	$((a * b)/d) * c$
$a^b+c*d$	$(a^b) + (c * d)$
$2^4!$	$2^{(4!)}$
$2*3!$	$2 * (3!)$

## 10.8 Flow Control

A computer language needs facilities for decision making and looping to control the order in which computations are done. **GAUSS** has several kinds of flow control statements.

### 10.8.1 Looping

#### do loop

The **do** statement can be used in **GAUSS** to control looping.

```
do while scalar_expression; /* loop if expression is true */
    .
    .
    statements
    .
    .
endo;
```

also

```
do until scalar_expression; /* loop if expression is false */
    .
    .
    statements
    .
    .
endo;
```

The *scalar\_expression* is any expression that returns a scalar result. The expression will be evaluated as TRUE if its real part is nonzero and FALSE if it is zero. There is no counter variable that is automatically incremented in a **do** loop. If one is used, it must be set to its initial value before the loop is entered and explicitly incremented or decremented inside the loop.

The following example illustrates nested **do** loops that use counter variables.

```
format /rdn 1,0;
space = "      ";
comma = ",";
i = 1;
do while i <= 4;
    j = 1;
    do while j <= 3;
        print space i comma j;;
        j = j+1;
    endo;
    i = i+1;
    print;
endo;
```

This will print:

1, 1	1, 2	1, 3
2, 1	2, 2	2, 3
3, 1	3, 2	3, 3
4, 1	4, 2	4, 3

Use the relational and logical operators without the dot ‘.’ in the expression that controls a **do** loop. These operators always return a scalar result.

**break** and **continue** are used within **do** loops to control execution flow. When **break** is encountered, the program will jump to the statement following the **enddo**. This terminates the loop. When **continue** is encountered, the program will jump up to the top of the loop and reevaluate the **while** or **until** expression. This allows you to reiterate the loop without executing any more of the statements inside the loop:

```
do until eof(fp);          /* continue jumps here */
  x = packr(readr(fp,100));
  if scalmiss(x);
    continue;             /* iterate again */
  endif;
  s = s + sumc(x);
  count = count + rows(x);
  if count >= 10000;
    break;                /* break out of loop */
  endif;
enddo;
mean = s / count;         /* break jumps here */
```

## for loop

The fastest looping construct in **GAUSS** is the **for** loop:

```
for counter (start, stop, step);  
    .  
    .  
    statements  
    .  
    .  
endfor;
```

*counter* is the literal name of the counter variable. *start*, *stop* and *step* are scalar expressions. *start* is the initial value, *stop* is the final value and *step* is the increment.

**break** and **continue** are also supported by **for** loops. (For more information, see **for** in the GAUSS LANGUAGE REFERENCE.)

### 10.8.2 Conditional Branching

The **if** statement controls conditional branching:

```
if scalar_expression;  
    .  
    .  
    statements  
    .  
    .  
elseif scalar_expression;  
    .  
    .  
    statements  
    .  
    .
```

```
else;  
    .  
    .  
    statements  
    .  
    .  
endif;
```

The *scalar\_expression* is any expression that returns a scalar result. The expression will be evaluated as TRUE if its real part is nonzero and FALSE if it is zero.

**GAUSS** will test the expression after the **if** statement. If it is TRUE, then the first list of statements is executed. If it is FALSE, then **GAUSS** will move to the expression after the first **elseif** statement, if there is one, and test it. It will keep testing expressions and will execute the first list of statements that corresponds to a TRUE expression. If no expression is TRUE, then the list of statements following the **else** statement is executed. After the appropriate list of statements is executed, the program will go to the statement following the **endif** and continue on.

Use the relational and logical operators without the dot ‘.’ in the expression that controls an **if** or **elseif** statement. These operators always return a scalar result.

**if** statements can be nested.

One **endif** is required per **if** clause. If an **else** statement is used, there may be only one per **if** clause. There may be as many **elseif**’s as are required. There need not be any **elseif**’s or any **else** statement within an **if** clause.

### 10.8.3 Unconditional Branching

The **goto** and **gosub** statements control unconditional branching. The target of both a **goto** and a **gosub** is a label.

#### **goto**

A **goto** is an unconditional jump to a label with no return:

```
label:
    .
    .
goto label;
```

Parameters can be passed with a **goto**. The number of parameters is limited by available stack space. This is helpful for common exit routines:

```
    .
    .
goto errout("Matrix singular");
    .
    .
goto errout("File not found");
    .
    .
errout:
    pop errmsg;
    errorlog errmsg;
end;
```

### **gosub**

With a **gosub**, the address of the **gosub** statement is remembered and when a **return** statement is encountered, the program will resume executing at the statement following the **gosub**.

Parameters can be passed with a **gosub** in the same way as a **goto**. With a **gosub** it is also possible to return parameters with the **return** statement.

Subroutines are not isolated from the rest of your program and the variables referred to between the label and the **return** statement can be accessed from other places in your program.

Since a subroutine is only an address marked by a label, there can be subroutines inside of procedures. The variables used in these subroutines are the same variables that are known inside the procedure. They will not be unique to the subroutine, but they may be locals that are unique to



the procedure that the subroutine is in. (For details, see **gosub** in the GAUSS LANGUAGE REFERENCE.)

## 10.9 Functions

Single line functions that return one item can be defined with the **fn** statement.

```
fn area(r) = pi * r * r;
```

These functions can be called in the same way as intrinsic functions. The above function could be used in the following program sequence.

```
diameter = 3;  
radius = 3 / 2;  
a = area(radius);
```

## 10.10 Rules of Syntax

This section lists the general rules of syntax for **GAUSS** programs.

### 10.10.1 Statements

A **GAUSS** program consists of a series of statements. A statement is a complete expression or command. Statements in **GAUSS** end with a semicolon with one exception: from the **GAUSS** command line, the final semicolon in an interactive program is implicit if it is not explicitly given:

```
(gauss) x=5; z=rndn(3,3); y=x+z
```

Column position is not significant. Blank lines are allowed. Inside a statement and outside of double quotes, the carriage return/line feed at the end of a physical line will be converted to a space character as the program is compiled.

A statement containing a quoted string can be continued across several lines with a backslash as follows.

```
s = "This is one really long string that would be "\
    "difficult to assign in just a single line.";
```

### 10.10.2 Case

**GAUSS** does not distinguish between uppercase and lowercase except inside double quotes.

### 10.10.3 Comments

```
// This comments out all text between the '//' and the end of
// the line
```

```
/* This kind of comment can be nested */
```

```
@ We consider this kind of comment to be obsolete, but it is
  supported for backwards compatibility @
```

### 10.10.4 Extraneous Spaces

Extraneous spaces are significant in **print** and **lprint** statements where the space is a delimiter between expressions:

```
print x y z;
```

In **print** and **lprint** statements, spaces can be used in expressions that are in parentheses:

```
print (x * y) (x + y);
```

### 10.10.5 Symbol Names

The names of matrices, strings, procedures, and functions can be up to 32 characters long. The characters must be alphanumeric or an underscore. The first character must be alphabetic or an underscore.

### 10.10.6 Labels

A label is used as the target of a **goto** or a **gosub**. The rules for naming labels are the same as for matrices, strings, procedures, and functions. A label is followed immediately by a colon:

```
here:
```

The reference to a label does not use a colon:

```
goto here;
```

### 10.10.7 Assignment Statements

The assignment operator is the equal sign '=':

```
y = x + z;
```

Multiple assignments must be enclosed in braces '{ }':

```
mant,pow = base10(x);
```

The comparison operator (equal to) is two equal signs '==':

```
if x == y;  
    print "x is equal to y";  
endif;
```

### 10.10.8 Function Arguments

The arguments to functions are enclosed in parentheses '( )':

```
y = sqrt(x);
```

### 10.10.9 Indexing Matrices

Brackets '[ ]' are used to index matrices:

```
x = { 1 2 3,  
      3 7 5,  
      3 7 4,  
      8 9 5,  
      6 1 8 };  
  
y = x[3,3];  
z = x[1 2:4,1 3];
```

Vectors can be indexed with either one or two indices:

```
v = 1 2 3 4 5 6 7 8 9 ;  
k = v[3];  
j = v[1,6:9];
```

**`x[2,3]`** returns the element in the second row and the third column of **`x`**.

**`x[1 3 5,4 7]`** returns the submatrix that is the intersection of rows 1, 3, and 5 and columns 4 and 7.

**`x[:,3]`** returns the third column of **`x`**.

**`x[3:5,.]`** returns the submatrix containing the third through the fifth rows of **`x`**.

The indexing operator will take vector arguments for submatrix extraction or submatrix assignments:

```
y = x[rv,cv];
```

```
y[rv,cv] = x;
```

**`rv`** and **`cv`** can be any expressions returning vectors or matrices. The elements of **`rv`** will be used as the row indices and the elements of **`cv`** will be used as the column indices. If **`rv`** is a scalar 0, all rows will be used; if **`cv`** is a scalar 0, all columns will be used. If a vector is used in an index expression, it is illegal to use the space operator or the colon operator on the same side of the comma as the vector.

### 10.10.10 Arrays of Matrices and Strings

It is possible to index sets of matrices or strings using the **`varget`** function.

In this example, a set of matrix names is assigned to **`mvec`**. The name **`y`** is indexed from **`mvec`** and passed to **`varget`** which will return the global matrix **`y`**. The returned matrix is inverted and assigned to **`g`**:

```
mvec = { x y z a };  
i = 2;  
g = inv(varget(mvec[i]));
```

The following procedure can be used to index the matrices in **mvec** more directly:

```
proc imvec(i);  
    retp(varget(mvec[i]));  
endp;
```

Then **imvec(i)** will equal the matrix whose name is in the  $i^{th}$  element of **mvec**.

In the example above, the procedure **imvec()** was written so that it always operates on the vector **mvec**. The following procedure makes it possible to pass in the vector of names being used:

```
proc get(array,i);  
    retp(varget(array[i]));  
endp;
```

Then **get(mvec,3)** will return the 3<sup>rd</sup> matrix listed in **mvec**.

```
proc put(x,array,i);  
    retp(varput(x,array[i]));  
endp;
```

And **put(x,mvec,3)** will assign **x** to the 3<sup>rd</sup> matrix listed in **mvec** and return a 1 if successful or a 0 if it fails.

### 10.10.11 Arrays of Procedures

It is also possible to index procedures. The ampersand operator (**&**) is used to return a pointer to a procedure.

Assume that **f1**, **f2**, and **f3** are procedures that take a single argument. The following code defines a procedure **fi** that will return the value of the  $i^{th}$  procedure, evaluated at **x**.

```
nms = &f1 | &f2 | &f3;

proc fi(x,i);
    local f;
    f = nms[i];
    local f:proc;
    retp( f(x) );
endp;
```

**fi(x,2)** will return **f2(x)**. The ampersand is used to return the pointers to the procedures. **nms** is a numeric vector that contains a set of pointers. The **local** statement is used twice. The first tells the compiler that **f** is a local matrix. The  $i^{th}$  pointer, which is just a number, is assigned to **f**. Then the second **local** statement tells the compiler to treat **f** as a procedure from this point on; thus the subsequent statement **f(x)** is interpreted as a procedure call.





# Operators 11

## 11.1 Element-by-Element Operators

Element-by-element operators share common rules of conformability. Some functions that have two arguments also operate according to the same rules.

Element-by-element operators handle those situations in which matrices are not conformable according to standard rules of matrix algebra. When a matrix is said to be  $E \times E$  conformable, it refers to this element-by-element conformability. The following cases are supported:

*matrix* **op** *matrix*

*matrix* **op** *scalar*

*scalar* **op** *matrix*

*matrix* **op** *vector*

*vector* **op** *matrix*

*vector* **op** *vector*

In a typical expression involving an element-by-element operator

$$z = x + y;$$

conformability is defined as follows:

- If  $x$  and  $y$  are the same size, the operations are carried out corresponding element by corresponding element:

$$x = \begin{array}{ccc} 1 & 3 & 2 \\ 4 & 5 & 1 \\ 3 & 7 & 4 \end{array}$$

$$y = \begin{array}{ccc} 2 & 4 & 3 \\ 3 & 1 & 4 \\ 6 & 1 & 2 \end{array}$$

$$z = \begin{array}{ccc} 3 & 7 & 5 \\ 7 & 6 & 5 \\ 9 & 8 & 6 \end{array}$$

- If  $x$  is a matrix and  $y$  is a scalar, or vice versa, then the scalar is operated on with respect to every element in the matrix. For example,  $x + 2$  will add 2 to every element of  $x$ :

$$x = \begin{array}{ccc} 1 & 3 & 2 \\ 4 & 5 & 1 \\ 3 & 7 & 4 \end{array}$$

$$y = 2$$

$$z = \begin{array}{ccc} 3 & 5 & 4 \\ 6 & 7 & 3 \\ 5 & 9 & 6 \end{array}$$

- If  $x$  is an  $N \times 1$  column vector and  $y$  is an  $N \times K$  matrix, or vice versa, the vector is swept “across” the matrix:

vector		matrix		
1	→	2	4	3
4	→	3	1	4
3	→	6	1	2
		result		
		3	5	4
		7	5	8
		9	4	5

- If  $x$  is an  $1 \times K$  row vector and  $y$  is an  $N \times K$  matrix, or vice versa, then the vector is swept “down” the matrix:

vector	2 4 3		
	↓	↓	↓
matrix	2	4	3
	3	1	4
	6	1	2
result	4	8	6
	5	5	7
	8	5	5

- When one argument is a row vector and the other is a column vector, the result of an element-by-element operation will be the “table” of the two:

row vector		2	4	3	1
		<hr/>			
	3	5	7	6	4
column vector	2	4	6	5	3
	5	7	9	8	6

If  $x$  and  $y$  are such that none of these conditions apply, the matrices are not conformable to these operations and an error message will be generated.

## 11.2 Matrix Operators

The following operators work on matrices. Some assume numeric data and others will work on either character or numeric data.

### 11.2.1 Numeric Operators

For details on how matrix conformability is defined for element-by-element operators, see ELEMENT-BY-ELEMENT OPERATORS, Section [11.1](#).

**+**     Addition

$$y = x + z;$$

Performs element-by-element addition.

**–**     Subtraction or negation

$$\begin{aligned}y &= x - z; \\y &= -k;\end{aligned}$$

Performs element-by-element subtraction or the negation of all elements, depending on context.

**\*** Matrix multiplication or multiplication

$$y = x * z;$$

When  $z$  has the same number of rows as  $x$  has columns, this will perform matrix multiplication (inner product). If  $x$  or  $z$  are scalar, this performs standard element-by-element multiplication.

**/** Division or linear equation solution

$$x = b / A;$$

If  $A$  and  $b$  are scalars, this performs standard division. If one of the operands is a matrix and the other is scalar, the result is a matrix the same size with the results of the divisions between the scalar and the corresponding elements of the matrix. Use `./` for element-by-element division of matrices.

If  $b$  and  $A$  are conformable, this operator solves the linear matrix equation

$$Ax = b$$

Linear equation solution is performed in the following cases:

- If  $A$  is a square matrix and has the same number of rows as  $b$ , this statement will solve the system of linear equations using an LU decomposition.
- If  $A$  is rectangular with the same number of rows as  $b$ , this statement will produce the least squares solutions by forming the normal equations and using the Cholesky decomposition to get the solution:

$$x = \frac{A'b}{A'A}$$

If **trap** 2 is set, missing values will be handled with pairwise deletion.

**%** Modulo division

$$y = x \%z;$$

For integers, this returns the integer value that is the remainder of the integer division of  $x$  by  $z$ . If  $x$  or  $z$  is noninteger, it will first be rounded to the nearest integer. This is an element-by-element operator.

### ! Factorial

$$y = x!;$$

Computes the factorial of every element in the matrix  $x$ . Nonintegers are rounded to the nearest integer before the factorial operator is applied. This will not work with complex matrices. If  $x$  is complex, a fatal error will be generated.

### . \* Element-by-element multiplication

$$y = x .* z;$$

If  $x$  is a column vector, and  $z$  is a row vector (or vice versa), the “outer product” or “table” of the two will be computed. (For conformability rules, see [ELEMENT-BY-ELEMENT OPERATORS](#), Section [11.1](#).)

### ./ Element-by-element division

$$y = x ./ z;$$

### ^ Element-by-element exponentiation

$$y = x^z;$$

If  $x$  is negative,  $z$  must be an integer.

### . ^ Same as ^

### . \*. Kronecker (tensor) product

$$y = x \text{ .* } z;$$

This results in a matrix in which every element in  $x$  has been multiplied (scalar multiplication) by the matrix  $z$ . For example:

$$x = \begin{Bmatrix} 1 & 2 \\ 3 & 4 \end{Bmatrix};$$

$$z = \begin{Bmatrix} 4 & 5 & 6 \\ 7 & 8 & 9 \end{Bmatrix};$$

$$y = x \text{ .* } z;$$

$$x = \begin{bmatrix} 1 & 2 \\ 3 & 4 \end{bmatrix}$$

$$z = \begin{bmatrix} 4 & 5 & 6 \\ 7 & 8 & 9 \end{bmatrix}$$

$$y = \begin{bmatrix} 4 & 5 & 6 & 8 & 10 & 12 \\ 7 & 8 & 9 & 14 & 16 & 18 \\ 12 & 15 & 18 & 16 & 20 & 24 \\ 21 & 24 & 27 & 28 & 32 & 36 \end{bmatrix}$$

~ Horizontal direct product

$$z = x \text{ *~ } y;$$

$$x = \begin{bmatrix} 1 & 2 \\ 3 & 4 \end{bmatrix}$$

$$y = \begin{bmatrix} 5 & 6 \\ 7 & 8 \end{bmatrix}$$

$$z = \begin{array}{cccc} 5 & 6 & 10 & 12 \\ 21 & 24 & 28 & 32 \end{array}$$

The input matrices  $x$  and  $y$  must have the same number of rows. The result will have **cols( $x$ ) \* cols( $y$ )** columns.

### 11.2.2 Other Matrix Operators

- / Transpose operator

$$y = x';$$

The columns of  $y$  will contain the same values as the rows of  $x$  and the rows of  $y$  will contain the same values as the columns of  $x$ . For complex matrices this computes the complex conjugate transpose.

If an operand immediately follows the transpose operator, the  $'$  will be interpreted as  $'*$ . Thus  $y = x'x$  is equivalent to  $y = x'*x$ .

- .' Bookkeeping transpose operator

$$y = x.';$$

This is provided primarily as a matrix handling tool for complex matrices. For all matrices, the columns of  $y$  will contain the same values as the rows of  $x$  and the rows of  $y$  will contain the same values as the columns of  $x$ . The complex conjugate transpose is NOT computed when you use  $.'$ .

If an operand immediately follows the bookkeeping transpose operator, the  $.'$  will be interpreted as  $.*$ . Thus  $y = x.'x$  is equivalent to  $y = x.*x$ .

- | Vertical concatenation

$$z = x|y;$$

$$x = \begin{array}{ccc} 1 & 2 & 3 \\ 3 & 4 & 5 \end{array}$$



---

```
y = 7 8 9
```

```
      1 2 3
z =   3 4 5
      7 8 9
```

~ Horizontal concatenation

```
z = x~y;
```

```
x =  1 2
     3 4
```

```
y =  5 6
     7 8
```

```
z =  1 2 5 6
     3 4 7 8
```

## 11.3 Relational Operators

For details on how matrix conformability is defined for element-by-element operators, see [ELEMENT-BY-ELEMENT OPERATORS](#), Section [11.1](#)

Each of these operators has two equivalent representations. Either can be used (for example, `<` or `lt`), depending only upon preference. The alphabetic form should be surrounded by spaces.

A third form of these operators has a `$` and is used for comparisons between character data and for comparisons between strings or string arrays. The comparisons are done byte by byte starting with the lowest addressed byte of the elements being compared.

The equality comparison operators (`<=`, `==`, `>=`, `/=`) and their dot equivalents can be used to test for missing values and the NaN that is created by floating point exceptions. Less than and greater

than comparisons are not meaningful with missings or NaN's, but equal and not equal are valid. These operators are sign-insensitive for missings, NaN's, and zeros.

The string '\$' versions of these operators can also be used to test missings, NaN's and zeros. Because they do a strict byte-to-byte comparison, they are sensitive to the sign bit. Missings, NaN's, and zeros can all have the sign bit set to 0 or 1, depending on how they were generated and have been used in a program.

If the relational operator is NOT preceded by a dot '.', then the result is always a scalar 1 or 0, based upon a comparison of all elements of  $x$  and  $y$ . All comparisons must be true for the relational operator to return TRUE.

By this definition, then

```
if x /= y;
```

is interpreted as: "if every element of  $x$  is not equal to the corresponding element of  $y$ ". To check if two matrices are not identical, use

```
if not x == y;
```

For complex matrices, the ==, /=, .== and ./= operators compare both the real and imaginary parts of the matrices; all other relational operators compare only the real parts.

- Less than

```
z = x < y;
```

```
z = x lt y;
```

```
z = x $< y;
```

- Less than or equal to

```
z = x <= y;
```

$$z = x \text{ le } y;$$
$$z = x \text{ \$<=} y;$$

- Equal to

$$z = x \text{ == } y;$$
$$z = x \text{ eq } y;$$
$$z = x \text{ \$== } y;$$

- Not equal

$$z = x \text{ /= } y;$$
$$z = x \text{ ne } y;$$
$$z = x \text{ \$/=} y;$$

- Greater than or equal to

$$z = x \text{ >=} y;$$
$$z = x \text{ ge } y;$$
$$z = x \text{ \$>=} y;$$

- Greater than

$$z = x \text{ >} y;$$
$$z = x \text{ gt } y;$$
$$z = x \text{ \$>} y;$$

If the relational operator IS preceded by a dot '.', then the result will be a matrix of 1's and 0's, based upon an element-by-element comparison of  $x$  and  $y$ .

- Element-by-element less than

$$z = x \text{ .<} y;$$
$$z = x \text{ .lt } y;$$
$$z = x \text{ .\$<} y;$$

- Element-by-element less than or equal to

$$z = x \text{ .<=} y;$$
$$z = x \text{ .le } y;$$
$$z = x \text{ .\$<=} y;$$

- Element-by-element equal to

$$z = x \text{ .== } y;$$
$$z = x \text{ .eq } y;$$
$$z = x \text{ .\$== } y;$$

- Element-by-element not equal to

$$z = x \text{ ./=} y;$$
$$z = x \text{ .ne } y;$$
$$z = x \text{ .\$/= } y;$$

- Element-by-element greater than or equal to

$$z = x \text{ .>=} y;$$
$$z = x \text{ .ge } y;$$
$$z = x \text{ .\$>=} y;$$

- Element-by-element greater than

```
z = x .> y;
```

```
z = x .gt y;
```

```
z = x .> y;
```

11.4 Logical Operators

The logical operators perform logical or Boolean operations on numeric values. On input a nonzero value is considered TRUE and a zero value is considered FALSE. The logical operators return a 1 if TRUE and a 0 if FALSE. Decisions are based on the following truth tables:

Complement

X	not X
T	F
F	T

Conjunction

X	Y	X and Y
T	T	T
T	F	F
F	T	F
F	F	F

**Disjunction**

<i>X</i>	<i>Y</i>	<i>X or Y</i>
T	T	T
T	F	T
F	T	T
F	F	F

**Exclusive Or**

<i>X</i>	<i>Y</i>	<i>X xor Y</i>
T	T	F
T	F	T
F	T	T
F	F	F

**Equivalence**

<i>X</i>	<i>Y</i>	<i>X eqv Y</i>
T	T	T
T	F	F
F	T	F
F	F	T

For complex matrices, the logical operators consider only the real part of the matrices.

The following operators require scalar arguments. These are the ones to use in **if** and **do** statements:

- Complement

`z = not x;`

- Conjunction

`z = x and y;`

- Disjunction

`z = x or y;`

- Exclusive or

`z = x xor y;`

- Equivalence

`z = x eqv y;`

If the logical operator is preceded by a dot '.', the result will be a matrix of 1's and 0's based upon an element-by-element logical comparison of  $x$  and  $y$ :

- Element-by-element logical complement

`z = .not x;`

- Element-by-element conjunction

`z = x .and y;`

- Element-by-element disjunction

`z = x .or y;`

- Element-by-element exclusive or

`z = x .xor y;`

- Element-by-element equivalence

`z = x .eqv y;`

## 11.5 Other Operators

### Assignment Operator

Assignments are done with one equal sign:

```
y = 3;
```

### Comma

Commas are used to delimit lists:

```
clear x,y,z;
```

to separate row indices from column indices within brackets:

```
y = x[3,5];
```

and to separate arguments of functions within parentheses:

```
y = momentd(x,d);
```

### Period

Dots are used in brackets to signify “all rows” or “all columns”:

```
y = x[.,5];
```



## Space

Spaces are used inside of index brackets to separate indices:

```
y = x[1 3 5,3 5 9];
```

No extraneous spaces are allowed immediately before or after the comma, or immediately after the left bracket or before the right bracket.

Spaces are also used in **print** and **lprint** statements to separate the separate expressions to be printed:

```
print x/2 2*sqrt(x);
```

No extraneous spaces are allowed within expressions in **print** or **lprint** statements unless the expression is enclosed in parentheses:

```
print (x / 2) (2 * sqrt(x));
```

## Colon

A colon is used within brackets to create a continuous range of indices:

```
y = x[1:5,.];
```

## Ampersand

The (&) ampersand operator will return a pointer to a procedure (**proc**), function (**fn**), or structure (**struct**). It is used when passing procedures or functions to other functions, when indexing procedures, and when initializing structure pointers. (For more information, see INDEXING PROCEDURES, Section 12.5 or STRUCTURE POINTERS, Section 13.2.)

### String Concatenation

```
x = "dog";  
y = "cat";  
z = x $+ y;  
print z;
```

dogcat

If the first argument is of type string, the result will be of type string. If the first argument is of type matrix, the result will be of type matrix. Here are some examples:

```
y = 0 $+ "caterpillar";
```

The result will be a 1×1 matrix containing ‘caterpil’.

```
y = zeros(3,1) $+ "cat";
```

The result will be a 3×1 matrix, each element containing ‘cat’.

If we use the *y* created above in the following:

```
k = y $+ "fish";
```

The result will be a 3×1 matrix with each element containing ‘catfish’.

If we then use *k* created above:

```
t = "" $+ k[1,1];
```

The result will be a string containing ‘catfish’.

If we used the same *k* to create *z* as follows:

---

```
z = "dog" $+ k[1,1];
```

The resulting `z` will be a string containing 'dogcatfish'.

## String Array Concatenation

`$|` Vertical string array concatenation

```
x = "dog";
y = "fish";
k = x $| y;
print k;
```

```
dog
fish
```

`$~` Horizontal string array concatenation

```
x = "dog";
y = "fish";
k = x $~ y;
print k;
```

```
dog          fish
```

## String Variable Substitution

In a command like the following:

```
create f1 = olsdat with x,4,2;
```

by default **GAUSS** will interpret **olsdat** as the literal name of the **GAUSS** data file you want to create. It will also interpret **x** as the literal prefix string for the variable names **x1 x2 x3 x4**.

To get the data set name from a string variable, the substitution operator (^) could be used as follows:

```
dataset = "olsdat";  
create f1 = ^dataset with x,4,2;
```

To get the data set name from a string variable and the variable names from a character vector, use the following:

```
dataset = "olsdat";  
vnames = { age, pay, sex };  
create f1 = ^dataset with ^vnames,0,2;
```

The general syntax is:

*^variable\_name*

Expressions are not allowed.

The following commands are currently supported with the substitution operator (^) in the current version.

```
create f1 = ^dataset with ^vnames,0,2;  
create f1 = ^dataset using ^cmdfile;  
open f1 = ^dataset;  
output file = ^outfile;  
load x = ^datafile;  
load path = ^lpath x,y,z,t,w;  
loadexe buf = ^exefile;  
save ^name = x;  
save path = ^spath;  
dos ^cmdstr;  
run ^prog;  
msym ^mstring;
```

## 11.6 Using Dot Operators with Constants

When you use those operators preceded by a `'.'` (dot operators) with a scalar integer constant, insert a space between the constant and any following dot operator. Otherwise, the dot will be interpreted as part of the scalar; that is, the decimal point. For example:

```
let y = 1 2 3;
x = 2.<y;
```

will return **x** as a scalar 0, not a vector of 0's and 1's, because

```
x = 2.<y;
```

is interpreted as

```
x = 2. < y;
```

and not as

```
x = 2 .< y;
```

Be careful when using the dot relational operators (`.<`, `.<=`, `.==`, `./=`, `.>`, `.>=`). The same problem can occur with other dot operators, also. For example:

```
let x = 1 1 1;
y = x./2./x;
```

will return **y** as a scalar .5 rather than a vector of .5's, because

$$y = x ./ 2 ./ x;$$

is interpreted as

$$y = (x ./ 2.) / x;$$

not

$$y = (x ./ 2) ./ x;$$

The second division, then, is handled as a matrix division rather than an element-by-element division.

## 11.7 Operator Precedence

The order in which an expression is evaluated is determined by the precedence of the operators involved and the order in which they are used. For example, the **\*** and **/** operators have a higher precedence than the **+** and **-** operators. In expressions that contain the above operators, the operand pairs associated with the **\*** or **/** operator are evaluated first. Whether **\*** or **/** is evaluated first depends on which comes first in the particular expression.

The expression

$$-5+3/4+6*3$$

is evaluated as

$$(-5)+(3/4)+(6*3)$$

Within a term, operators of equal precedence are evaluated from left to right. The precedence of all operators, from the highest to the lowest, is listed in the following table:

Operator	Precedence	Operator	Precedence	Operator	Precedence
<code>./</code>	90	<code>.\$&gt;=</code>	65	<code>\$&gt;=</code>	55
<code>/</code>	90	<code>./=</code>	65	<code>/=</code>	55
<code>!</code>	89	<code>.&lt;</code>	65	<code>&lt;</code>	55
<code>.^</code>	85	<code>.&lt;=</code>	65	<code>&lt;=</code>	55
<code>^</code>	85	<code>.==</code>	65	<code>==</code>	55
<b>(unary -)</b>	83	<code>.&gt;</code>	65	<code>&gt;</code>	55
<code>*</code>	80	<code>.&gt;=</code>	65	<code>&gt;=</code>	55
<code>*~</code>	80	<code>.eq</code>	65	<code>eq</code>	55
<code>.*</code>	80	<code>.ge</code>	65	<code>ge</code>	55
<code>.*.</code>	80	<code>.gt</code>	65	<code>gt</code>	55
<code>./</code>	80	<code>.le</code>	65	<code>le</code>	55
<code>/</code>	80	<code>.lt</code>	65	<code>lt</code>	55
<code>%</code>	75	<code>.ne</code>	65	<code>ne</code>	55
<code>\$+</code>	70	<code>.not</code>	64	<code>not</code>	49
<code>+</code>	70	<code>.and</code>	63	<code>and</code>	48
<code>-</code>	70	<code>.or</code>	62	<code>or</code>	47
<code>~</code>	68	<code>.xor</code>	61	<code>xor</code>	46
<code> </code>	67	<code>.eqv</code>	60	<code>eqv</code>	45
<code>.\$/=</code>	65	<code>\$/=</code>	55	<b>(space)</b>	35
<code>.\$&lt;</code>	65	<code>\$&lt;</code>	55	<code>:</code>	35
<code>.\$&lt;=</code>	65	<code>\$&lt;=</code>	55	<code>=</code>	10
<code>.\$==</code>	65	<code>\$==</code>	55		
<code>.\$&gt;</code>	65	<code>\$&gt;</code>	55		





# Procedures and Keywords 12

Procedures are multiple-line, recursive functions that can have either local or global variables. Procedures allow a large computing task to be written as a collection of smaller tasks. These smaller tasks are easier to work with and keep the details of their operation from the other parts of the program that do not need to know them. This makes programs easier to understand and easier to maintain.

A procedure in **GAUSS** is basically a user-defined function that can be used as if it were an intrinsic part of the language. A procedure can be as small and simple or as large and complicated as necessary to perform a particular task. Procedures allow you to build on your previous work and on the work of others rather than starting over again and again to perform related tasks.

Any intrinsic command or function may be used in a procedure, as well as any user-defined function or other procedure. Procedures can refer to any global variable; that is, any variable in the global symbol table that can be shown with the **show** command. It is also possible to declare local variables within a procedure. These variables are known only inside the procedure they are defined in and cannot be accessed from other procedures or from the main level program code.

All labels and subroutines inside a procedure are local to that procedure and will not be confused with labels of the same name in other procedures.

## 12.1 Defining a Procedure

A procedure definition consists of five parts, four of which are denoted by explicit **GAUSS** commands:

- |                                |                        |
|--------------------------------|------------------------|
| 1. Procedure declaration       | <b>proc</b> statement  |
| 2. Local variable declaration  | <b>local</b> statement |
| 3. Body of procedure           |                        |
| 4. Return from procedure       | <b>retp</b> statement  |
| 5. End of procedure definition | <b>endp</b> statement  |

There is always one **proc** statement and one **endp** statement in a procedure definition. Any statements that come between these two statements are part of the procedure. Procedure definitions cannot be nested. **local** and **retp** statements are optional. There can be multiple **local** and **retp** statements in a procedure definition. Here is an example:

```
proc (3) = regress(x, y);  
    local xxi,b,ymxb,sse,sd,t;  
    xxi = invpd(x'x);  
    b = xxi * (x'y);  
    ymxb = y-xb;  
    sse = ymxb'ymxb/(rows(x)-cols(x));  
    sd = sqrt(diag(sse*xxi));  
    t = b./sd;  
    retp(b,sd,t);  
endp;
```

This could be used as a function that takes two matrix arguments and returns three matrices as a result. For example: is:

```
{ b,sd,t } = regress(x,y);
```

Following is a discussion of the five parts of a procedure definition.

### 12.1.1 Procedure Declaration

The **proc** statement is the procedure declaration statement. The format is:

```
proc [(rets) =] name([arg1,arg2,...argN]);
```

<i>rets</i>	Optional constant, number of values returned by the procedure. Acceptable values here are 0-1023; the default is 1.
<i>name</i>	Name of the procedure, up to 32 alphanumeric characters or an underscore, beginning with an alpha or an underscore.
<i>arg#</i>	Names that will be used inside the procedure for the arguments that are passed to the procedure when it is called. There can be 0-1023 arguments. These names will be known only in the procedure being defined. Other procedures can use the same names, but they will be separate entities.

### 12.1.2 Local Variable Declarations

The **local** statement is used to declare local variables. Local variables are variables known only to the procedure being defined. The names used in the argument list of the **proc** statement are always local. The format of the **local** statement is:

```
local x,y,f:proc,g:fn,z,h:keyword;
```

Local variables can be matrices or strings. If **:proc**, **:fn**, or **:keyword** follows the variable name in the **local** statement, the compiler will treat the symbol as if it were a procedure, function, or keyword respectively. This allows passing procedures, functions, and keywords to other procedures. (For more information, see [PASSING PROCEDURES TO PROCEDURES](#), Section [12.4](#).)

Variables that are global to the system (that is, variables listed in the global symbol table that can be shown with the **show** command) can be accessed by any procedure without any redundant declaration inside the procedure. If you want to create variables known only to the procedure

being defined, the names of these local variables must be listed in a **local** statement. Once a variable name is encountered in a **local** statement, further references to that name inside the procedure will be to the local rather than to a global having the same name. (See **clearg**, **varget**, and **varput** in the GAUSS LANGUAGE REFERENCE for ways of accessing globals from within procedures that have locals with the same name.)

The **local** statement does not initialize (set to a value) the local variables. If they are not passed in as parameters, they must be assigned some value before they are accessed or the program will terminate with a **Variable not initialized** error message.

All local and global variables are dynamically allocated and sized automatically during execution. Local variables, including those that were passed as parameters, can change in size during the execution of the procedure.

Local variables exist only when the procedure is executing and then disappear. Local variables cannot be listed with the **show** command.

The maximum number of locals is limited by stack space and the size of workspace memory. The limiting factor applies to the total number of active local symbols at any one time during execution. If **cat** has 10 locals and it calls **dog** which has 20 locals, there are 30 active locals whenever **cat** is called.

There can be multiple **local** statements in a procedure. They will affect only the code in the procedure that follows. Therefore, for example, it is possible to refer to a global **x** in a procedure and follow that with a **local** statement that declares a local **x**. All subsequent references to **x** would be to the local **x**. (This is not good programming practice, but it demonstrates the principle that the **local** statement affects only the code that is physically below it in the procedure definition.) Another example is a symbol that is declared as a local and then declared as a local procedure or function later in the same procedure definition. This allows doing arithmetic on local function pointers before calling them. (For more information, see INDEXING PROCEDURES, Section 12.5.

### 12.1.3 Body of Procedure

The body of the procedure can have any **GAUSS** statements necessary to perform the task the procedure is being written for. Other user-defined functions and other procedures can be referenced as well as any global matrices and strings.

**GAUSS** procedures are recursive, so the procedure can call itself as long as there is logic in the procedure to prevent an infinite recursion. The process would otherwise terminate with either an **Insufficient workspace memory** message or a **Procedure calls too deep** message, depending on the space necessary to store the locals for each separate invocation of the procedure.

### 12.1.4 Returning from the Procedure

The return from the procedure is accomplished with the **retp** statement:

```
retp;
```

```
retp(expression1, expression2, ..., expressionN);
```

The **retp** statement can have multiple arguments. The number of items returned must coincide with the number of *rets* in the **proc** statement.

If the procedure was defined with no items returned, the **retp** statement is optional. The **endp** statement that ends the procedure will generate an implicit **retp** with no objects returned. If the procedure returns one or more objects, there must be an explicit **retp** statement.

There can be multiple **retp** statements in a procedure, and they can be anywhere inside the body of the procedure.

### 12.1.5 End of Procedure Definition

The **endp** statement marks the end of the procedure definition:

```
endp;
```

An implicit **retp** statement that returns nothing is always generated here so it is impossible to run off the end of a procedure without returning. If the procedure was defined to return one or more objects, executing this implicit return will result in a **Wrong number of returns** error message and the program will terminate.

## 12.2 Calling a Procedure

Procedures are called like this:

```
dog(i,j,k);                /* no returns */  
  
y = cat(i,j,k);            /* one return */  
  
{ x,y,z } = bat(i,j,k);    /* multiple returns */  
  
call bat(i,j,k);           /* ignore any returns */
```

Procedures are called in the same way that intrinsic functions are called. The procedure name is followed by a list of arguments in parentheses. The arguments must be separated by commas.

If there is to be no return value, use

```
proc (0) = dog(x,y,z);
```

when defining the procedure and use

```
dog(ak,4,3);
```

or

```
call dog(ak,4,3);
```

when calling it.

The arguments passed to procedures can be complicated expressions involving calls to other functions and procedures. This calling mechanism is completely general. For example,

```
y = dog(cat(3*x,bird(x,y))-2,2,1);
```

is legal.

## 12.3 Keywords

A keyword, like a procedure, is a subroutine that can be called interactively or from within a **GAUSS** program. A keyword differs from a procedure in that a keyword accepts exactly one string argument, and returns nothing. Keywords can perform many tasks not as easily accomplished with procedures.

### 12.3.1 Defining a Keyword

A keyword definition is much like a procedure definition. Keywords always are defined with 0 returns and 1 argument. The beginning of a keyword definition is the **keyword** statement:

```
keyword name(strarg);
```

*name*        Name of the keyword, up to 32 alphanumeric characters or an underscore, beginning with an alpha or an underscore.

*strarg*     Name that will be used inside of the keyword for the argument that is passed to the keyword when it is called. There is always one argument. The name is known only in the keyword being defined. Other keywords can use the same name, but they will be separate entities. This will always be a string. If the keyword is called with no characters following the name of the keyword, this will be a null string.

The rest of the keyword definition is the same as a procedure definition. (For more information, see **DEFINING A PROCEDURE**, Section 12.1. Keywords always return nothing. Any **retp** statements, if used, should be empty. For example:

```
keyword add(s);
    local tok, sum;

    if s $== "";
        print "The argument is a null string";
        retp;
    endif;

    print "The argument is: '" s "'";

    sum = 0;
    do until s $== "";
        { tok, s } = token(s);
        sum = sum + stof(tok);
    endo;
    format /rd 1,2;
    print "The sum is:      " sum;
endp;
```

The keyword defined above will print the string argument passed to it. The argument will be printed enclosed in single quotes.

### 12.3.2 Calling a Keyword

When a keyword is called, every character up to the end of the statement, excluding the leading spaces, is passed to the keyword as one string argument. For example, if you type

```
add 1 2 3 4 5;
```

the keyword will respond

```
The sum is:  15.00
```



Here is another example:

```
add;
```

the keyword will respond

```
The argument is a null string
```

## 12.4 Passing Procedures to Procedures

Procedures and functions can be passed to procedures in the following way:

```
proc max(x,y); /* procedure to return maximum */
  if x>y;
    retp(x);
  else;
    retp(y);
  endif;
endp;

proc min(x,y); /* procedure to return minimum */
  if x<y;
    retp(x);
  else;
    retp(y);
  endif;
endp;

fn lgsqrt(x) = ln(sqrt(x)); /* function to return
                             :: log of square root
                             */
```

```
proc myproc(&f1,&f2,x,y);  
    local f1:proc, f2:fn, z;  
    z = f1(x,y);  
    retp(f2(z));  
endp;
```

The procedure **myproc** takes four arguments. The first is a procedure **f1** that has two arguments. The second is a function **f2** that has one argument. It also has two other arguments that must be matrices or scalars. In the **local** statement, **f1** is declared to be a procedure and **f2** is declared to be a function. They can be used inside the procedure in the usual way. **f1** will be interpreted as a procedure inside **myproc**, and **f2** will be interpreted as a function. The call to **myproc** is made as follows:

```
k = myproc(&max,&lgsqrt,5,7); /* log of square root of 7 */  
  
k = myproc(&min,&lgsqrt,5,7); /* log of square root of 5 */
```

The ampersand (&) in front of the function or procedure name in the call to **myproc** causes a pointer to the function or procedure to be passed. No argument list should follow the name when it is preceded by the ampersand.

Inside **myproc**, the symbol that is declared as a procedure in the **local** statement is assumed to contain a pointer to a procedure. It can be called exactly like a procedure is called. It cannot be **save**'d but it can be passed on to another procedure. If it is to be passed on to another procedure, use the ampersand in the same way.

## 12.5 Indexing Procedures

This example assumes there are a set of procedures named **f1-f5** that are already defined. A 1×5 vector **procvec** is defined by horizontally concatenating pointers to these procedures. A new procedure, **g(x,i)** is then defined to return the value of the  $i^{th}$  procedure evaluated at  $x$ :

```
procvec = &f1 ~ &f2 ~ &f3 ~ &f4 ~ &f5;
```

```
proc g(x,i);  
    local f;  
    f = procvec[i];  
    local f:proc;  
    retp( f(x) );  
endp;
```

The **local** statement is used twice. The first time, **f** is declared to be a local matrix. After **f** has been set equal to the  $i^{th}$  pointer, **f** is declared to be a procedure and is called as a procedure in the **retp** statement.

## 12.6 Multiple Returns from Procedures

Procedures can return multiple items, up to 1023. The procedure is defined like this example of a complex inverse:

```
proc (2) = cminv(xr,xi); /* (2) specifies number of  
                        :: return values  
                        */  
    local ixy, zr, zi;  
    ixy = inv(xr)*xi;  
    zr = inv(xr+xi*ixy); /* real part of inverse. */  
    zi = -ixy*zr;        /* imaginary part of inverse. */  
    retp(zr,zi);        /* return: real part, imaginary part */  
endp;
```

It can then be called like this:

```
{ zr,zi } = cminv(xr,xi);
```

To make the assignment, the list of targets must be enclosed in braces.

Also, a procedure that returns more than one argument can be used as input to another procedure or function that takes more than one argument:

```
proc (2) = cminv(xr,xi);
    local ixy, zr, zi;
    ixy = inv(xr)*xi;
    zr = inv(xr+xi*ixy); /* real part of inverse. */
    zi = -ixy*zr;        /* imaginary part of inverse. */
    retp(zr,zi);
endp;

proc (2) = cmmult(xr,xi,yr,yi);
    local zr,zi;
    zr = xr*yr-xi*yi;
    zi = xr*yi+xi*yr;
    retp(zr,zi);
endp;

{ zr,zi } = cminv( cmmult(xr,xi,yr,yi) );
```

The two returned matrices from **cmmult()** are passed directly to **cminv()** in the statement above. This is equivalent to the following statements:

```
{ tr,ti } = cmmult(xr,xi,yr,yi);
{ zr,zi } = cminv(tr,ti);
```

This is completely general so the following program is legal:

```
proc (2) = cmcplx(x);
    local r,c;
    r = rows(x);
    c = cols(x);
    retp(x,zeros(r,c));
endp;
```

```
proc (2) = cminv(xr,xi);
    local ixy, zr, zi;
    ixy = inv(xr)*xi;
    zr = inv(xr+xi*ixy); /* real part of inverse. */
    zi = -ixy*zr;        /* imaginary part of inverse. */
    retp(zr,zi);
endp;

proc (2) = cmmult(xr,xi,yr,yi);
    local zr,zi;
    zr = xr*yr-xi*yi;
    zi = xr*yi+xi*yr;
    retp(zr,zi);
endp;

{ xr,xi } = cmcplx(rndn(3,3));
{ yr,yi } = cmcplx(rndn(3,3));

{ zr,zi } = cmmult( cminv(xr,xi),cminv(yr,yi) );
{ qr,qi } = cmmult( yr,yi,cminv(yr,yi) );

{ wr,wi } = cmmult(yr,yi,cminv(cmmult(cminv(xr,xi),yr,yi)));
```

## 12.7 Saving Compiled Procedures

When a file containing a procedure definition is run, the procedure is compiled and is then resident in memory. The procedure can be called as if it were an intrinsic function. If the **new** command is executed or you quit **GAUSS** and exit to the operating system, the compiled image of the procedure disappears and the file containing the procedure definition will have to be compiled again.

If a procedure contains no global references, that is, if it does not reference any global matrices or strings and it does not call any user-defined functions or procedures, it can be saved to disk in compiled form in a **.fcg** file with the **save** command, and loaded later with the **loadp** command

whenever it is needed. This will usually be faster than recompiling. For example:

```
save path = c:\gauss\cp proc1,proc2,proc3;
```

```
loadp path = c:\gauss\cp proc1,proc2,proc3;
```

The name of the file will be the same as the name of the procedure, with a .fcg extension. (For details, see **loadp** and **save** in the GAUSS LANGUAGE REFERENCE.)

All compiled procedures should be saved in the same subdirectory, so there is no question where they are located when it is necessary to reload them. The **loadp** path can be set in your startup file to reflect this. Then, to load in procedures, use

```
loadp proc1,proc2,proc3;
```

Procedures that are saved in .fcg files will NOT be automatically loaded. It is necessary to explicitly load them with **loadp**. This feature should be used only when the time necessary for the autoloader to compile the source is too great. Also, unless these procedures have been compiled with **#lineson**, debugging will be more complicated.

# Structures 13

## 13.1 Basic Structures

### 13.1.1 Structure Definition

The syntax for a structure definition is

```
struct A { /* list of members */ };
```

The list of members can include scalars, arrays, matrices, strings, and string arrays, as well as other structures. As a type, scalars are unique to structures and don't otherwise exist.

For example, the following defines a structure containing the possible contents:

```
struct generic_example {  
    scalar x;  
    matrix y;
```

```
string s1;  
string array s2  
struct other_example t;  
};
```

A useful convention is to put the structure definition into a file with a `.sdf` extension. Then, for any command file or source code file that requires this definition, put

```
#include filename.sdf
```

For example:

```
#include example.sdf
```

These statements create structure definitions that persist until the workspace is cleared. They do not create structures, only structure-type definitions. The next section describes how to create an instance of a structure.

### 13.1.2 Declaring an Instance

To use a structure, it is necessary to declare an instance. The syntax for this is

```
struct structure_type structure_name;
```

For example:

```
#include example.sdf  
struct generic_example p0;
```



### 13.1.3 Initializing an Instance

Members of structures are referenced using a “dot” syntax:

```
p0.x = rndn(20,3);
```

The same syntax applies when referred to on the right-hand side:

```
mn = mean(p0.x);
```

### Initialization of Global Structures

Global structures are initialized at compile time. Each member of the structure is initialized according to the following schedule:

scalar	0, a scalar zero
matrix	, an empty matrix with zero rows and zero columns
array	0, a 1-dimensional array set to zero
string	"", a null string
string array	"", a 1×1 string array set to null

If a global already exists in memory, it will not be reinitialized. It may be the case in your program that when it is rerun, the global variables may need to be reset to default values. That is, your program may depend on certain members of a structure being set to default values that are set to some other value later in the program. When you rerun this program, you will want to reinitialize the global structure. To do this, make an assignment to at least one of the members. This can be made convenient by writing a procedure that declares a structure and initializes one of its members to a default value, and then returns it. For example:

```
/* ds.src */
#include ds.sdf

proc dsCreate;
```

```
    struct DS d0;  
    d0.dataMatrix = 0;  
    retp(d0);  
endp;
```

Calling this function after declaring an instance of the structure will ensure initialization to default values each time your program is run:

```
struct DS d0;  
d0 = dsCreate;
```

### Initializing Local Structures

Local structures, which are structures defined inside procedures, are initialized at the first assignment. The procedure may have been written in such a way that a subset of structures are used on any one call, and in that case time is saved by not initializing the unused structures. They will be initialized to default values only when the first assignment is made to one of its members.

#### 13.1.4 Arrays of Structures

To create a matrix of instances, use the **reshape** command:

```
#include ds.sdf  
struct DS p0;  
p0 = reshape(dsCreate,5,1);
```

This creates a 5×1 vector of instances of **DS** structures, with all of the members initialized to default values.

When the instance members have been set to some other values, **reshape** will produce multiple copies of that instance set to those values.

Matrices or vectors of instances can also be created by concatenation:

```
#include trade.sdf
struct option p0,p1,p2;

p0 = optionCreate;
p1 = optionCreate;
p2 = p1 | p0;
```

### 13.1.5 Structure Indexing

Structure indexing may be used to reference a particular element in a structure array. The syntax follows that of matrix indexing. For example, given the following structure definition:

```
struct example1 {
    matrix x;
    matrix y;
    string str;
};
```

you could create an array of **example1** structures and index it as follows:

```
struct example1 e1a;
struct example1 e1b;

e1a = e1a | e1b;
e1a[2,1].y = randn(25,10);
```

In this example, **e1a** and **e1b** are concatenated to create a 2×1 array of **example1** structures that is assigned back to **e1a**. Then the **y** member of the [2,1] element of **e1a** is set to a random matrix.

Indexing of structure arrays can occur on multiple levels. For example, let's define the following structures:

```
struct example3 {
```

```
        matrix w;  
        string array sa;  
    };  
  
    struct example2 {  
        matrix z;  
        struct example3 e3;  
    };  
};
```

and let's redefine **example1** to include an instance of an **example2** structure:

```
struct example1 {  
    matrix x;  
    matrix y;  
    string str;  
    struct example2 e2;  
};
```

Let's assume that we have an **example1** structure **e1** like the one displayed in Figure 13.1. We could then index the structure as follows:


```
r = e1.e2[3,1].e3[2,1].w
```

You can also use indexing to reference the structure itself, rather than a member of that structure:

```
struct example3 e3tmp;  
e3tmp = e1.e2[3,1].e3[2,1];
```

Or you can use indexing to reference a subarray of structures:

```
e3tmp = e1.e2[3,1].e3[.,1];
```

Figure 13.1: Structure tree for **e1**

In this case, **e3tmp** would be an array of  $3 \times 1$  **example3** structures, since the [3,1] member of **e1.e2** contains a  $3 \times 1$  array of **example3** structures.

It is important to remember, however, that when indexing a structure array on multiple levels, only the final index may resolve to an array of structures. For example:

```
e3tmp = e1.e2[.,1].e3[2,1];
```

would be invalid, since **e1.e2[.,1]** resolves to a  $3 \times 1$  array of **example2** structures.

### 13.1.6 Saving an Instance to the Disk

Instances and vectors or matrices of instances of structures can be saved in a file on the disk, and later loaded from the file onto the disk. The syntax for saving an instance to the disk is

```
ret = savestruct(instance,filename);
```

The file on the disk will have an **.fsr** extension.

For example:

```
#include ds.sdf
struct DS p0;

p0 = reshape(dsCreate,2,1);
retc = saveStruct(p2,"p2");
```

This saves the vector of instances in a file called **p2.fsr**. **retc** will be zero if the save was successful; otherwise, nonzero.

### 13.1.7 Loading an Instance from the Disk

The syntax for loading a file containing an instance or matrix of instances is

```
instance, retc = loadstruct(file_name,structure_name);
```

For example:

```
#include trade.sdf;  
struct DS p3;  
{ p3, retc } = loadstruct("p2","ds");
```

### 13.1.8 Passing Structures to Procedures

Structures or members of structures can be passed to procedures. When a structure is passed as an argument to a procedure, it is passed by value. The structure becomes a local copy of the structure that was passed. The data in the structure is not duplicated unless the local copy of the structure has a new value assigned to one of its members. Structure arguments must be declared in the procedure definition:

```
struct rectangle {  
    matrix ulx;  
    matrix uly;  
    matrix lrx;  
    matrix lry;  
};  
  
proc area(struct rectangle rect);  
    retp((rect.lrx - rect.ulx).*(rect.uly - rect.lry));  
endp;
```

Local structures are defined using a **struct** statement inside the procedure definition:

```
proc center(struct rectangle rect);
    struct rectangle cent;

    cent.lrx = (rect.lrx - rect.ulx) / 2;
    cent.ulx = -cent.lrx;
    cent.uly = (rect.uly - rect.lry) / 2;
    cent.lry = -cent.uly;
    retp(cent);
endp;
```

## 13.2 Structure Pointers

A structure pointer is a separate data type that contains the address of a structure and is used to reference that structure.

### 13.2.1 Creating and Assigning Structure Pointers

Given the following structure type definition:

```
struct example_struct {
    matrix x;
    matrix y;
};
```

a pointer to an **example\_struct** structure can be created with the following syntax:

```
struct example_struct *esp;
```

However, at this point, **esp** is not yet pointing at anything. It has only been defined to be the kind of pointer that points at **example\_struct** structures. To set it to point at a particular structure instance, we must first create the structure instance:



---

```
struct example_struct es;
```

and then we can set **esp** to point at **es** by setting **esp** to the address of **es**:

```
esp = &es;
```

The following code:

```
struct example_struct es2;  
es2 = *esp;
```

copies the contents of the structure that **esp** is pointing at (i.e., the contents of **es**) to **es2**. It is the same as

```
struct example_struct es2;  
es2 = es;
```

### 13.2.2 Structure Pointer References

To reference a member of a structure, we use a “dot” syntax. For example, we might use the following code to set the **x** member of **es**.

```
es.x = rndn(3,3);
```

To reference a member of a structure using a pointer to that structure, we use an “arrow” syntax. For example, we might use the following code to set the **x** member of **es** using the pointer **esp**:

```
esp->x = rndn(10,5);
```

This code will modify **es**, since **esp** is merely a pointer to **es**.

Structure pointers cannot be members of a structure. The following is illegal:

```
struct example_struct_2 {  
    matrix z;  
    struct example_struct *ep;  
};
```

Therefore, since a structure pointer will never be a member of a structure, neither

```
sp1->sp2->x;
```

nor

```
s.sp1->x;
```

will ever be valid (**sp1** and **sp2** are assumed to be structure pointers, **s** a structure instance, and **x** a matrix). The “arrow” (**->**) will only be valid if it is used for the first (or furthest left) dereference, as in:

```
sp1->st.x;
```

At this point we do not support indexing of structure pointers. Thus, a structure pointer should point at a scalar structure instance, not a matrix of structures. However, you may index members of that scalar structure instance. So, for example, let us suppose that you defined the following structure types:

```
struct sb {  
    matrix y;  
    matrix z;
```

```
};

struct sa {
    matrix x;
    struct structb s;
};
```

and then created an instance of an **sa** structure, **a0**, setting **a0.s** to a 3×2 matrix of **sb** structures. The following would be legal:

```
struct sa *sap
sap = &a0;
sap->s[3,1].y = rndn(3,3);
```

### 13.2.3 Using Structure Pointers in Procedures

Structure pointers are especially useful in cases where structures are passed into and out of procedures. If a procedure takes a structure as an argument and modifies any members of that structure, then it makes a local copy of the entire structure before modifying it. Thus if you want to have the modified copy of the structure after running the procedure, you need to pass the structure out of the procedure as one of its return arguments. For example:

```
struct example_struct {
    matrix x;
    matrix y;
    matrix z;
};

proc product(struct example_struct es);
    es.z = (es.x).*(es.y);
    retp(es);
endp;

struct example_struct es1;
```

```
es1.x = rndn(1000,100);  
es1.y = rndn(1000,1);  
es1 = product(es1);
```

In this example, the structure **es1** is passed into the procedure, copied and modified. The modified structure is then passed out of the procedure and assigned back to **es1**.

Structure pointers allow you to avoid such excessive data copying and eliminate the need to pass a structure back out of a procedure in cases like this. When you pass a structure pointer into a procedure and then modify a member of the structure that it references, the actual structure is modified rather than a local copy of it. Thus there is no need to pass the modified structure back out of the procedure. For example, the above example could be accomplished using structure pointers as follows:

```
struct example_struct {  
    matrix x;  
    matrix y;  
    matrix z;  
};  
  
proc(0) = product(struct example_struct *esp);  
    esp->z = (esp->x).*(esp->y);  
endp;  
  
struct example_struct es1;  
struct example_struct *es1p;  
  
es1p = &es1;  
es1.x = rndn(1000,100);  
es1.y = rndn(1000,1);  
product(es1p);
```

In this case, the procedure modifies the structure **es1**, which **es1p** is pointing at, instead of a local copy of the structure.

## 13.3 Special Structures

There are three common types of structures that will be found in the **GAUSS Run-Time Library** and applications.

The **DS** and **PV** structures are defined in the **GAUSS Run-Time Library**. Their definitions are found in `ds.sdf` and `pv.sdf`, respectively, in the `src` source code subdirectory.

Before structures, many procedures in the **Run-Time Library** and all applications had global variables serving a variety of purposes, such as setting and altering defaults. Currently, these variables are being entered as members of “control” structures.

### 13.3.1 The DS Structure

The **DS** structure, or “data” structure, is a very simple structure. It contains a member for each **GAUSS** data type. The following is found in `ds.sdf`:

```
struct DS {  
    scalar type;  
    matrix dataMatrix;  
    array dataArray;  
    string dname;  
    string array vnames;  
};
```

This structure was designed for use by the various optimization functions in **GAUSS**, in particular, **sqpSolve****mt**, as well as a set of gradient procedures, **gradmt**, **hessmt**, et al.

These procedures all require that the user provide a procedure computing a function (to be optimized or take the derivative of, etc.), which takes the **DS** structure as an argument. The **Run-Time Library** procedures such as **sqpSolve****mt** take the **DS** structure as an argument and pass it on to the user-provided procedure without modification. Thus, the user can put into that structure whatever might be needed as data in the procedure.

To initialize an instance of a **DS** structure, the procedure **dsCreate** is defined in `ds.src`:

```
#include ds.sdf
struct DS d0;
d0 = dsCreate;
```

### 13.3.2 The PV Structure

The **PV** structure, or *parameter vector* structure, is used by various optimization, modelling, and gradient procedures, in particular **sqpSolvemt**, for handling the parameter vector. The **GAUSS Run-Time Library** contains special functions that work with this structure. They are prefixed by “pv” and defined in `pv.src`. These functions store matrices and arrays with parameters in the structure, and retrieve various kinds of information about the parameters and parameter vector from it.

#### “Packing” into a PV Structure

The various procedures in the **Run-Time Library** and applications for optimization, modelling, derivatives, etc., all require a parameter vector. Parameters in complex models, however, often come in matrices of various types, and it has been the responsibility of the programmer to generate the parameter vector from the matrices and vice versa. The **PV** procedures make this problem much more convenient to solve.

The typical situation involves two parts: first, “packing” the parameters into the **PV** structure, which is then passed to the **Run-Time Library** procedure or application; and second, “unpacking” the **PV** structure in the user-provided procedure for use in computing the objective function. For example, to pack parameters into a **PV** structure:

```
#include sqpsolvemt.sdf

/* starting values */

b0 = 1; /* constant in mean equation */
garch = { .1, .1 }; /* garch parameters */
arch = { .1, .1 }; /* arch parameters */
omega = .1 /* constant in variance equation */
```

```

struct PV p0;

p0 = pvPack(pvCreate,b0,"b0");
p0 = pvPack(p0,garch,"garch");
p0 = pvPack(p0,arch,"arch");
p0 = pvPack(p0,omega,"omega");

/* data */

z = loadd("tseries");

struct DS d0;
d0.dataMatrix = z;

```

Next, in the user-provided procedure for computing the objective function, in this case minus the log-likelihood, the parameter vector is unpacked:

```

proc ll(struct PV p0, struct DS d0);
    local b0,garch,arch,omega,p,q,h,u,vc,w;

    b0 = pvUnpack(p0,"b0");
    garch = pvUnpack(p0,"garch");
    arch = pvUnpack(p0,"arch");
    omega = pvUnpack(p0,"omega");

    p = rows(garch);
    q = rows(arch);

    u = d0.dataMatrix - b0;
    vc = moment(u,0)/rows(u);
    w = omega + (zeros(q,q) | shiftr((u.*ones(1,q))',
        seqa(q-1,-1,q))) * arch;
    h = recserar(w,vc*ones(p,1),garch);
    logl = -0.5 * ((u.*u)./h + ln(2*pi) + ln(h));

    retp(logl);

```

```
endp;
```

### Masked Matrices

The **pvUnpack** function unpacks parameters into matrices or arrays for use in computations. The first argument is a **PV** structure containing the parameter vector. Sometimes the matrix or vector is partly parameters to be estimated (that is, a parameter to be entered in the parameter vector) and partly fixed parameters. To distinguish between estimated and fixed parameters, an additional argument is used in the packing function called a “mask”, which is strictly conformable to the input matrix. Its elements are set to 1 for an estimated parameter and 0 for a fixed parameter. For example:

```
p0 = pvPackm(p0, .1*eye(3), "theta", eye(3));
```

Here just the diagonal of a 3×3 matrix is added to the parameter vector.

When this matrix is unpacked, the entire matrix is returned with current values of the parameters on the diagonal:

```
print pvUnpack(p0, "theta");
```

```
0.1000  0.0000  0.0000
0.0000  0.1000  0.0000
0.0000  0.0000  0.1000
```

### Symmetric Matrices

Symmetric matrices are a special case because even if the entire matrix is to be estimated, only the nonredundant portion is to be put into the parameter vector. Thus, for them there are special procedures. For example:



---

```
vc = { 1 .6 .4, .6 1 .2, .4 .2 1 };
p0 = pvPacks(p0,vc,"vc");
```

There is also a procedure for masking in case only a subset of the nonredundant elements are to be included in the parameter vector:

```
vc = { 1 .6 .4, .6 1 .2, .4 .2 1 };
mask = { 1 1 0, 1 1 0, 0 0 1 };
p0 = pvPacksm(p0,vc,"vc",mask);
```

## Fast Unpacking

When unpacking matrices using a matrix name, **pvUnpack** has to make a search through a list of names, which is relatively time-consuming. This can be alleviated by using an index rather than a name in unpacking. To do this, though, requires using a special pack procedure that establishes the index:

```
p0 = pvPacki(p0,b0,"b0",1);
p0 = pvPacki(p0,garch,"garch",2);
p0 = pvPacki(p0,arch,"arch",3);
p0 = pvPacki(p0,omega,"omega",4);
Now they may be unpacked using the index number:
b0 = pvUnpack(p0,1);
garch = pvUnpack(p0,2);
arch = pvUnpack(p0,3);
omega = pvUnpack(p0,4);
```

When packed with an index number, they may be unpacked either by index or by name, but unpacking by index is faster.

### 13.3.3 Miscellaneous PV Procedures

#### **pvList**

This procedure generates a list of the matrices or arrays packed into the structure:

```
p0 = pvPack(p0,b0,"b0");  
p0 = pvPack(p0,garch,"garch");  
p0 = pvPack(p0,arch,"arch");  
p0 = pvPack(p0,omega,"omega");  
print pvList(p0);
```

```
b0  
garch  
arch  
omega
```

#### **pvLength**

This procedure returns the length of the parameter vector:

```
print pvLength(p0);  
  
6.0000
```

#### **pvGetParNames**

This procedure generates a list of parameter names:

```
print pvGetParNames(p0);
```

```
b0[1,1]
garch[1,1]
garch[2,1]
arch[1,1]
arch[2,1]
omega[1,1]
```

### **pvGetParVector**

This procedure returns the parameter vector itself:

```
print pvGetParVector(p0);

1.0000
0.1000
0.1000
0.1000
0.1000
0.1000
1.0000
```

### **pvPutParVector**

This procedure replaces the parameter vector with the one in the argument:

```
newp = { 1.5, .2, .2, .3, .3, .8 };
p0 = pvPutParVector(newp);
print pvGetParVector(p0);

1.5000
0.2000
0.2000
0.3000
0.3000
0.8000
```

### pvGetIndex

This procedure returns the indices in the parameter vector of the parameters in a matrix. These indices are useful when setting linear constraints or bounds in **sqpSolvemt**. Bounds, for example, are set by specifying a  $K \times 2$  matrix where  $K$  is the length of the parameter vector and the first column are the lower bounds and the second the upper bounds. To set the bounds for a particular parameter, then, requires knowing where that parameter is in the parameter vector. This information can be found using **pvGetIndex**. For example:

```
// get indices of lambda parameters in parameter vector
lind = pvGetIndex(par0,"lambda");

// set bounds constraint matrix to unconstrained default
c0.bounds = ones(pvLength(par0),1).*(-1e250~1e250);

// set bounds for lambda parameters to be positive
c0.bounds[lind,1] = zeros(rows(lind),1);
```

### 13.3.4 Control Structures

Another important class of structures is the “control” structure. Applications developed before structures were introduced into **GAUSS** typically handled some program specifications by the use of global variables which had some disadvantages, in particular, preventing the nesting of calls to procedures.

Currently, the purposes served by global variables are now served by the use of a control structure. For example, for **sqpSolvemt**:

```
struct sqpSolvemtControl {
    matrix A;
    matrix B;
    matrix C;
    matrix D;
    scalar eqProc;
    scalar ineqProc;
```

```

matrix bounds;
scalar gradProc;
scalar hessProc;
scalar maxIters;
scalar dirTol;
scalar CovType;
scalar feasibleTest;
scalar maxTries;
scalar randRadius;
scalar trustRadius;
scalar seed;
scalar output;
scalar printIters;
matrix weights;
};

```

The members of this structure determine optional behaviors of **sqpSolvemt**.

## 13.4 sqpSolvemt

**sqpSolvemt** is a procedure in the **GAUSS Run-Time Library** that solves the general nonlinear programming problem using a Sequential Quadratic Programming descent method, that is, it solves

$$\min f(\theta)$$

subject to

$A\theta = B$	linear equality
$C\theta \geq D$	linear inequality
$H(\theta) = 0$	nonlinear equality
$G(\theta) \geq 0$	nonlinear inequality
$\theta_{lb} \leq \theta \leq \theta_{ub}$	bounds

The linear and bounds constraints are redundant with respect to the nonlinear constraints, but are treated separately for computational convenience.

The call to **sqpSolveMT** has four input arguments and one output argument:

```
out = SQPsolveMT(&fct,P,D,C);
```

### 13.4.1 Input Arguments

The first input argument is a pointer to the objective function to be minimized. The procedure computing this objective function has two arguments: a **PV** structure containing the start values, and a **DS** structure containing data, if any. For example:

```
proc fct(struct PV p0, struct DS d0);  
    local y, x, b0, b, e, s;  
    y = d0[1].dataMatrix;  
    x = d0[2].dataMatrix;  
    b0 = pvUnpack(p0,"constant");  
    b = pvUnpack(p0,"coefficients");  
    e = y - b0 - x * b;  
    s = sqrt(e'e/rows(e));  
    retp(-pdfn(e/s);  
endp;
```

Note that this procedure returns a vector rather than a scalar. When the objective function is a properly defined log-likelihood, returning a vector of minus log-probabilities permits the calculation of a QML covariance matrix of the parameters.

The remaining input arguments are structures:

- |          |  |
|----------|--|
| <i>P</i> | a <b>PV</b> structure containing starting values of the parameters |
| <i>D</i> | a <b>DS</b> structure containing data, if any                      |

*C* an **sqpSolveMControl** structure

The **DS** structure is optional. **sqpSolveM** passes this argument on to the user-provided procedure that *Erfct* is pointing to without modification. If there is no data, a default structure can be passed to it.

### **sqpSolveMControl** Structure

A default **sqpSolveMControl** structure can be passed in the fourth argument for an unconstrained problem. The members of this structure are as follows:

<b>A</b>	M×K matrix, linear equality constraint coefficients: $A\theta = B$ , where $\theta$ is a vector of the parameters.
<b>B</b>	M×1 vector, linear equality constraint constants: $A\theta = B$ , where $\theta$ is a vector of the parameters.
<b>C</b>	M×K matrix, linear inequality constraint coefficients: $C\theta = D$ , where $\theta$ is a vector of the parameters.
<b>D</b>	M×1 vector, linear inequality constraint constants: $C\theta = D$ , where $\theta$ is a vector of the parameters.
<b>eqProc</b>	scalar, pointer to a procedure that computes the nonlinear equality constraints. When such a procedure has been provided, it has two input arguments, instances of <b>PV</b> and <b>DS</b> structures, and one output argument, a vector of computed inequality constraints. Default = .; i.e., no inequality procedure.
<b>IneqProc</b>	scalar, pointer to a procedure that computes the nonlinear inequality constraints. When such a procedure has been provided, it has two input arguments, instances of <b>PV</b> and <b>DS</b> structures, and one output argument, a vector of computed inequality constraints. Default = .; i.e., no inequality procedure.

Bounds	<p>1×2 or K×2 matrix, bounds on parameters. If 1×2 all parameters have same bounds.</p> <p>Default = -1e256 1e256 .</p>
GradProc	<p>scalar, pointer to a procedure that computes the gradient of the function with respect to the parameters. When such a procedure has been provided, it has two input arguments, instances of <b>PV</b> and <b>DS</b> structures, and one output argument, the derivatives. If the function procedure returns a scalar, the gradient procedure returns a 1×K row vector of derivatives. If function procedure turns an N×1 vector, the gradient procedure returns an N×K matrix of derivatives.</p> <p>This procedure may compute a subset of the derivatives. <b>sqpSolvemt</b> will compute numerical derivatives for all those elements set to missing values in the return vector or matrix.</p> <p>Default = .; i.e., no gradient procedure has been provided.</p>
HessProc	<p>scalar, pointer to a procedure that computes the Hessian; i.e., the matrix of second order partial derivatives of the function with respect to the parameters. When such a procedure has been provided, it has two input arguments, instances of <b>PV</b> and <b>DS</b> structures, and one output argument, a vector of computed inequality constraints.</p> <p>Default = .; i.e., no Hessian procedure has been provided.</p> <p>Whether the objective function procedure returns a scalar or vector, the Hessian procedure must return a K×K matrix. Elements set to missing values will be computed numerically by <b>sqpSolvemt</b>.</p>
MaxIters	<p>scalar, maximum number of iterations. Default = 1e+5.</p>
MaxTries	<p>scalar, maximum number of attempts in random search. Default = 100.</p>
DirTol	<p>scalar, convergence tolerance for gradient of estimated coefficients. Default = 1e-5. When this criterion has been satisfied, <b>sqpSolvemt</b> exits the iterations.</p>
CovType	<p>scalar, if 2, QML covariance matrix, else if 0, no covariance matrix is computed, else ML covariance matrix is computed. For a QML covariance matrix, the objective function procedure must return an N×1 vector of minus log-probabilities.</p>



---

<b>FeasibleTest</b>	scalar, if nonzero, parameters are tested for feasibility before computing function in line search. If function is defined outside inequality boundaries, then this test can be turned off. Default = 1.
<b>randRadius</b>	scalar, if zero, no random search is attempted. If nonzero, it is the radius of the random search. Default = .001.
<b>seed</b>	scalar, if nonzero, seeds random number generator for random search, otherwise time in seconds from midnight is used.
<b>trustRadius</b>	scalar, radius of the trust region. If scalar missing, trust region not applied. The trust sets a maximum amount of the direction at each iteration. Default = .001.
<b>output</b>	scalar, if nonzero, results are printed. Default = 0.
<b>PrintIters</b>	scalar, if nonzero, prints iteration information. Default = 0.
<b>weights</b>	vector, weights for objective function returning a vector. Default = 1.

### 13.4.2 Output Argument

The single output argument is an **sqpSolveMTOut** structure. Its definition is:

```
struct SQPsolveMTOut {
    struct PV par;
    scalar fct;
    struct SQPsolveMTLagrange lagr;
    scalar retcode;
    matrix moment;
    matrix hessian;
    matrix xproduct;
};
```

The members of this structure are:

**par** instance of a **PV** structure containing the parameter estimates are placed in the matrix member **par**.

**fct** scalar, function evaluated at final parameter estimates.

**lagr** an instance of an **SQLagrange** structure containing the Lagrangeans for the constraints. For an instance named **lagr**, the members are:

**lagr.lineq**  $M \times 1$  vector, Lagrangeans of linear equality constraints

**lagr.nlineq**  $N \times 1$  vector, Lagrangeans of nonlinear equality constraints

**lagr.linineq**  $P \times 1$  vector, Lagrangeans of linear inequality constraints

**lagr.nlinineq**  $Q \times 1$  vector, Lagrangeans of nonlinear inequality constraints

**lagr.bounds**  $K \times 2$  matrix, Lagrangeans of bounds

Whenever a constraint is active, its associated Lagrangean will be nonzero. For any constraint that is inactive throughout the iterations as well as at convergence, the corresponding Lagrangean matrix will be set to a scalar missing value.

**retcode** return code:

- 0** normal convergence
- 1** forced exit
- 2** maximum number of iterations exceeded
- 3** function calculation failed
- 4** gradient calculation failed
- 5** Hessian calculation failed
- 6** line search failed
- 7** error with constraints
- 8** function complex
- 9** feasible direction couldn't be found

### 13.4.3 Example

Define

$$Y = \Lambda\eta + \theta$$

where  $\Lambda$  is a  $K \times L$  matrix of *loadings*,  $\eta$  an  $L \times 1$  vector of unobserved “latent” variables, and  $\theta$  a  $K \times 1$  vector of unobserved errors. Then

$$\Sigma = \Lambda\Phi\Lambda'\Psi$$

where  $\Phi$  is the  $L \times L$  covariance matrix of the latent variables, and  $\Psi$  is the  $K \times K$  covariance matrix of the errors.

The log-likelihood of the  $i^{th}$  observation is

$$\log P(i) = -\frac{1}{2}[K\ln(2\pi) + \ln |\Sigma| + Y(i)\Sigma^{-1}Y(i)']$$

Not all elements of  $\Lambda$ ,  $\Phi$ , and  $\Psi$  can be estimated. At least one element of each column of  $\Lambda$  must be fixed to 1, and  $\Psi$  is usually a diagonal matrix.

### Constraints

To ensure a well-defined log-likelihood, constraints on the parameters are required to guarantee positive definite covariance matrices. To do this, a procedure is written that returns the eigenvalues of  $\Sigma$  and  $\Phi$  minus a small number. **sqpSolve** then finds parameters such that these eigenvalues are greater than or equal to that small number.

### 13.4.4 The Command File

This command file can be found in the file `sqpfact.e` in the `examples` subdirectory:

```
#include sqpsolvemt.sdf

lambda = { 1.0 0.0,
           0.5 0.0,
           0.0 1.0,
           0.0 0.5 };

lmask = { 0 0,
          1 0,
          0 0,
          0 1 };

phi = { 1.0 0.3,
        0.3 1.0 };

psi = { 0.6 0.0 0.0 0.0,
        0.0 0.6 0.0 0.0,
        0.0 0.0 0.6 0.0,
        0.0 0.0 0.0 0.6 };

tmask = { 1 0 0 0,
          0 1 0 0,
          0 0 1 0,
          0 0 0 1 };

struct PV par0;
par0 = pvCreate;
par0 = pvPackm(par0,lambda,"lambda",lmask);
par0 = pvPacks(par0,phi,"phi");
par0 = pvPacksm(par0,psi,"psi",tmask);

struct SQPsolveMTControl c0;
```

---

```

c0 = sqpSolveMTcontrolCreate;

lind = pvGetIndex(par0,"lambda"); /* get indices of lambda */
/* parameters in parameter */
/* vector */
tind = pvGetIndex(par0,"psi"); /* get indices of psi */
/* parameters in parameter */
/* vector */

c0.bounds = ones(pvLength(par0),1).*(-1e250~1e250);
c0.bounds[lind,1] = zeros(rows(lind),1);
c0.bounds[lind,2] = 10*ones(rows(lind),1);
c0.bounds[tind,1] = .001*ones(rows(tind),1);
c0.bounds[tind,2] = 100*ones(rows(tind),1);

c0.output = 1;
c0.printIters = 1;
c0.trustRadius = 1;
c0.ineqProc = &ineq;
c0.covType = 1;

struct DS d0;
d0 = dsCreate;
d0.dataMatrix = loadadd("maxfact");

output file = sqpfact.out reset;

struct SQPsolveMTOut out0;
out0 = SQPsolveMT(&lpr,par0,d0,c0);

lambdahat = pvUnpack(out0.par,"lambda");
phihat = pvUnpack(out0.par,"phi");
psihat = pvUnpack(out0.par,"psi");

print "estimates";
print;
print "lambda" lambdahat;

```

---

```
print;
print "phi" phihat;
print;
print "psi" psihat;

struct PV stderr;
stderr = out0.par;

if not scalmiss(out0.moment);
    stderr = pvPutParVector(stderr,sqrt(diag(out0.moment)));
    lambdase = pvUnpack(stderr,"lambda");
    phise = pvUnpack(stderr,"phi");
    psise = pvUnpack(stderr,"psi");
    print "standard errors";
    print;
    print "lambda" lambdase;
    print;
    print "phi" phise;
    print;
    print "psi" psise;
endif;

output off;

proc lpr(struct PV par1, struct DS data1);
    local lambda,phi,psi,sigma,logl;

    lambda = pvUnpack(par1,"lambda");
    phi = pvUnpack(par1,"phi");
    psi = pvUnpack(par1,"psi");
    sigma = lambda*phi*lambda' + psi;
    logl = -lnpdfmvn(data1.dataMatrix,sigma);

    retp(logl);
endp;

proc ineq(struct PV par1, struct DS data1);
```

---

```
    local lambda,phi,psi,sigma,e;

    lambda = pvUnpack(par1,"lambda");
    phi = pvUnpack(par1,"phi");
    psi = pvUnpack(par1,"psi");
    sigma = lambda*phi*lambda' + psi;
    e = eigh(sigma) - .001; /* eigenvalues of sigma */
    e = e | eigh(phi) - .001; /* eigenvalues of phi */

    retp(e);
endp;
```





# Run-Time Library Structures 14

Two structures are used by several **GAUSS Run-Time Library** functions for handling parameter vectors and data: the **PV** parameter structure and the **DS** data structure.

## 14.1 The PV Parameter Structure

The members of an instance of structure of type **PV** are all “private,” that is, not accessible directly to the user. It is designed to handle parameter vectors for threadsafe optimization functions. Entering and receiving parameter vectors, and accessing properties of this vector, are accomplished using special functions.

Suppose you are optimizing a function containing a  $K \times L$  matrix of coefficients. The optimization function requires a parameter vector but your function uses a  $K \times L$  matrix. Your needs and the needs of the optimization function can be both satisfied by an instance of the structure of type **PV**. For example:

```
struct PV p1;  
p1 = pvCreate;
```

```
x = zeros(4,3); /* on input contains start values, */
                /* on exit contains estimates      */
p1 = pvPack(p1,x,"coefficients");
```

The **pvCreate** function initializes **p1** to default values. **pvPack** enters the 4×3 matrix stored row-wise as a 12×1 parameter vector for the optimization function. The optimization program will pass the instance of the structure of type **PV** to your objective function.

By calling **pvUnpack** your 4×3 coefficient matrix is retrieved from the parameter vector. For example, in your procedure you have

```
x = pvUnpack(p1,"coefficients");
```

and now **x** is a 4×3 matrix of coefficients for your use in calculating the object function.

Suppose that your objective function has parameters to be estimated in a covariance matrix. The covariance matrix is a symmetric matrix where only the lower left portion contains unique values for estimation. To handle this, use **pvPacks**. For example:

```
struct PV p1;
p1 = pvCreate;

cov = { 1 .1 .1,
        .1 1 .1,
        .1 .1 1 };

p1 = pvPacks(p1,cov,"covariance");
```

Only the lower left portion of cov will be stored in the parameter vector. When the covariance matrix is unpacked, the parameters in the parameter vector will be entered into both the lower and upper portions of the matrix.

There may be cases where only a portion of a matrix being used to compute the objective function are parameters to be estimated. In this case use **pvPackm** with a “mask” matrix that contains ones where parameters are to be estimated and zeros otherwise. For example,

```

struct PV p1;
p1 = pvCreate;

cov = { 1  .5,
        .5  1 };

mask = { 0  1,
         1  0 };

p1 = pvPacksm(p1,cov,"correlation",mask);

```

Here only the one element in the lower left of **cov** is stored in the parameter vector. Suppose the optimization program sends a trial value for that parameter of, say, .45. When the matrix is unpacked in your procedure it will contain the fixed values associated with the zeros in the mask as well as the trial value in that part of the matrix associated with the ones. Thus,

```

print unpack(p1,"correlation");

      1.0000  .4500
      .4500  1.0000

```

A mask may also be used with general matrices to store a portion of a matrix in the parameter vector.

```

struct PV p1;
p1 = pvCreate;

m = { 0  .5  1,
       .5  0  .3 };

mask = { 0  1  1,
         1  0  0 };

p1 = pvPackm(p1,m,"coefficients",mask);

```

A **PV** instance can, of course, hold parameters from all these types of matrices: symmetric, masked symmetric, rectangular, and masked rectangular. For example:

```
lambda = { 1.0  0.0,
           0.5  0.0,
           0.0  1.0,
           0.0  0.5 };
```

```
lmask  = { 0  0,
           1  0,
           0  0,
           0  1 };
```

```
phi = { 1.0  0.3,
        0.3  1.0 };
```

```
theta = { 0.6  0.0  0.0  0.0,
          0.0  0.6  0.0  0.0,
          0.0  0.0  0.6  0.0,
          0.0  0.0  0.0  0.6 };
```

```
tmask = { 1  0  0  0,
          0  1  0  0,
          0  0  1  0,
          0  0  0  1 };
```

```
struct PV par0;
par0 = pvCreate;
par0 = pvPackm(par0,lambda,"lambda",lmask);
par0 = pvPacks(par0,phi,"phi");
par0 = pvPacksm(par0,theta,"theta",tmask);
```

It isn't necessary to know where in the parameter vector the parameters are located in order to use them in your procedure calculating the objective function. Thus:

```
lambda = pvUnpack(par1,"lambda");
```

```

phi = pvUnpack(par1,"phi");
theta = pvUnpack(par1,"theta");
sigma = lambda*phi*lambda' + theta;

```

Additional functions are available to retrieve information on the properties of the parameter vector. **pvGetParVector** and **pvPutParVector** get and put parameter vector from and into the **PV** instance, **pvGetParNames** retrieves names for the elements of the parameter vector, **pvList** returns the list of matrix names in the **PV** instance, **pvLength** the length of the parameter vector.

```

struct PV p1;
p1 = pvCreate;

cov = { 1  .5,
        .5  1 };

mask = { 0 1,
         1 0 };

p1 = pvPacksm(p1,cov,"correlation",mask);
print pvGetParVector(p1);

.5000

p1 = pvPutParVector(p1,.8);
print pvGetParVector(p1);

.8000

print pvUnpack(p1,"correlation");

1.0000  .8000
.8000  1.0000

print pvGetParNames(p1);

correlation[2,1]

```

```
print pvLength(p1);  
  
1.0000
```

Also, **pvTest** tests an instance to make sure it is properly constructed. **pvCreate** generates an initialized instance, and **pvGetIndex** returns the indices of the parameters of an input matrix in the parameter vector. This last function is most useful when constructing linear constraint indices for the optimization programs.

## 14.2 Fast Pack Functions

Unpacking matrices using matrix names is slow because it requires a string search through a string array of names. A set of special packing functions are provided that avoid the search altogether. These functions use a “table” of indices that you specify to find the matrix in the **PV** instance. For example:

```
struct PV p1;  
p1 = pvCreate(2);  
  
y = rndn(4,1);  
x = rndn(4,4);  
  
p1 = pvPacki(p1,y,"Y",1);  
p1 = pvPacki(p1,x,"X",2);  
  
print pvUnpack(p1,1);  
  
.3422  
.0407  
.5611  
.0953  
  
print pvUnpack(p1,"Y");
```

```
.3422
.0407
.5611
.0953
```

The call to **pvPacki** puts an entry in the table associating the matrix in its second argument with the index 1. As indicated above the matrix can be unpacked either by index or by name. Unpacking by index, however, is much faster than by name.

Note that the matrix can be unpacked using either the index or the matrix name.

There are index versions of all four of the packing functions, **pvPacki**, **pvPackmi**, **pvPacksi**, and **pvPacksmi**.

## 14.3 The DS Data Structure

An instance of the **DS** data structure contains the following members:

```
struct DS d0;
```

<b>d0.dataMatrix</b>	M×K matrix, data
<b>d0.dataArray</b>	N-dimensional array, data
<b>d0.type</b>	scalar
<b>d0.dname</b>	string
<b>d0.vnames</b>	string array

The definition and use of the elements of **d0** are determined by the particular application and are mostly up to the user. A typical use might use a vector of structures. For example, suppose the objective function requires a vector of observations on a dependent variable as well as on  $K$  independent variables. Then:

```
struct DS d0;  
d0 = dsCreate;  
  
y = rndn(20,1);  
x = rndn(20,5);  
  
d0 = reshape(d0,2,1);  
d0[1].dataMatrix = y;  
d0[2].dataMatrix = X;
```

The **d0** instance would be passed to the optimization program which then passes it to your procedure computing the objective function. For example:

```
proc lpr(struct PV p1, struct DS d1);  
    local u;  
    u = d0[1].dataMatrix - d0[2].dataMatrix * pvUnpack(p1,"beta");  
    retp(u'u);  
endp;
```

A particular application may require setting other members of the **DS** instance for particular purposes, but in general you may use them for your own purposes. For example, **d0.dname** could be set to a **GAUSS** dataset name from which you read the data in the objective function procedure, or **d0.vnames** could be set to the variable names of the columns of the data stored in **d0.dataMatrix**, or **d0.type** could be an indicator variable for the elements of a vector of **DS** instances.

The following are complete examples of the use of the **PV** and **DS** structures. The first example fits a set of data to the Micherlitz model. It illustrates packing and unpacking by index.

```
#include sqpsolvemt.sdf  
  
struct DS Y;  
Y = dsCreate;  
  
Y.dataMatrix = 3.183|
```



```

3.059|
2.871|
2.622|
2.541|
2.184|
2.110|
2.075|
2.018|
1.903|
1.770|
1.762|
1.550;

```

```

struct DS X;
X = dsCreate;

```

```

X.dataMatrix = seqa(1,1,13);

```

```

struct DS Z;
Z = reshape(Z,2,1);
Z[1] = Y;
Z[2] = X;

```

```

struct SQPsolveMTControl c1;
c1 = sqpSolveMTControlCreate; /* initializes */
                               /* default values */

```

```

c1.bounds = 0~100;           /* constrains parameters */
                               /* to be positive */

```

```

c1.CovType = 1;
c1.output = 1;
c1.printIters = 0;
c1.gradProc = &grad;

```

```

struct PV par1;
par1 = pvCreate(1);

```

```
start = { 2, 4, 2 };
par1 = pvPacki(par1,start,"Parameters",1);

struct SQPsolveMTout out1;
out1 = SQPsolveMT(&Micherlitz,par1,Z,c1);

estimates = pvGetParVector(out1.par);
print " parameter estimates ";
print estimates;
print;
print " standard errors ";
print sqrt(diag(out1.moment));

proc Micherlitz(struct PV par1,struct DS Z);
    local p0,e,s2;
    p0 = pvUnpack(par1,1);
    e = Z[1].dataMatrix - p0[1] - p0[2]*exp(-p0[3]
        *Z[2].dataMatrix);
    s2 = moment(e,0)/(rows(e)-1);
    retp( (2/rows(e))*(e.*e/s2 + ln(2*pi*s2)));
endp;

proc grad(struct PV par1, struct DS Z);
    local p0,e,e1,e2,e3,w,g,s2;

    p0 = pvUnpack(par1,1);
    w = exp(-p0[3]*Z[2].dataMatrix);
    e = z[1].dataMatrix - p0[1] - p0[2] * w;
    s2 = moment(e,0) / rows(e);
    e1 = - ones(rows(e),1);
    e2 = -w;
    e3 = p0[2]*Z[2].dataMatrix.*w;
    w = (1 - e.*e / s2) / rows(e);
    g = e.*e1 + w*(e'e1);
    g = g ~ (e.*e2 + w*(e'e2));
    g = g ~ (e.*e3 + w*(e'e3));
```

```
    retp(4*g/(rows(e)*s2));
endp;
```

This example estimates parameters of a “confirmatory factor analysis” model.

```
\#include sqpsolvemt.sdf

lambda = { 1.0  0.0,
           0.5  0.0,
           0.0  1.0,
           0.0  0.5 };

lmask  = { 0  0,
           1  0,
           0  0,
           0  1 };

phi = { 1.0  0.3,
        0.3  1.0 };

theta = { 0.6  0.0  0.0  0.0,
          0.0  0.6  0.0  0.0,
          0.0  0.0  0.6  0.0,
          0.0  0.0  0.0  0.6 };

tmask = { 1  0  0  0,
          0  1  0  0,
          0  0  1  0,
          0  0  0  1 };

struct PV par0;
par0 = pvCreate;

par0 = pvPackm(par0,lambda,"lambda",lmask);
par0 = pvPacks(par0,phi,"phi");
par0 = pvPacksm(par0,theta,"theta",tmask);
```

```
struct SQPsolveMTControl c0;
c0 = sqpSolveMTcontrolCreate;

lind = pvGetIndex(par0,"lambda"); /* get indices of */
                                   /* lambda parameters */
                                   /* in parameter vector */

tind = pvGetIndex(par0,"theta"); /* get indices of */
                                   /* theta parameters */
                                   /* in parameter vector */

c0.bounds = ones(pvLength(par0),1).*(-1e250~1e250);
c0.bounds[lind,1] = zeros(rows(lind),1);
c0.bounds[lind,2] = 10*ones(rows(lind),1);
c0.bounds[tind,1] = .001*ones(rows(tind),1);
c0.bounds[tind,2] = 100*ones(rows(tind),1);

c0.ineqProc = &ineq;
c0.covType = 1;

struct DS d0;
d0 = dsCreate;

d0.dataMatrix = loadadd("maxfact");

struct SQPsolveMTOut out0;
out0 = SQPsolveMT(&lpr,par0,d0,c0);

lambdahat = pvUnpack(out0.par,"lambda");
phihat = pvUnpack(out0.par,"phi");
thetahat = pvUnpack(out0.par,"theta");

print "estimates";
print;
print "lambda" lambdahat;
print;
```

```

print "phi" phihat;
print;
print "theta" thetahat;

struct PV stderr;
stderr = out0.par;

if not scalmiss(out0.moment);
    stderr =
        pvPutParVector(stderr, sqrt(diag(out0.moment)));
    lambdase = pvUnpack(stderr, "lambda");
    phise = pvUnpack(stderr, "phi");
    thetase = pvUnpack(stderr, "theta");

    print "standard errors";
    print;
    print "lambda" lambdase;
    print;
    print "phi" phise;
    print;
    print "theta" thetase;
endif;

proc lpr(struct PV par1, struct DS data1);
    local lambda, phi, theta, sigma, logl;

    lambda = pvUnpack(par1, "lambda");
    phi = pvUnpack(par1, "phi");
    theta = pvUnpack(par1, "theta");
    sigma = lambda*phi*lambda' + theta;
    logl = -lnpdfmvn(data1.dataMatrix, sigma);

    retp(logl);
endp;

```

```
proc ineq(struct PV par1, struct DS data1);
    local lambda,phi,theta,sigma,e;

    lambda = pvUnpack(par1,"lambda");
    phi = pvUnpack(par1,"phi");
    theta = pvUnpack(par1,"theta");
    sigma = lambda*phi*lambda' + theta;

    e = eigh(sigma) - .001; /* eigenvalues of sigma */
    e = e | eigh(phi) - .001; /* eigenvalues of phi */

    retp(e);
endp;
```

# N-Dimensional Arrays 15

In **GAUSS**, internally, matrices and arrays are separate data types. Matrices, which are 2-dimensional objects, are stored in memory in row major order. Therefore, a  $3 \times 2$  matrix is stored as follows:

[1, 1] [1, 2] [2, 1] [2, 2] [3, 1] [3, 2]

The slowest moving dimension in memory is indexed on the right, and the fastest moving dimension is indexed on the left. This is true of N-dimensional arrays as well. A  $4 \times 3 \times 2$  array is stored in the following way:

[1, 1, 1] [1, 1, 2] [1, 2, 1] [1, 2, 2] [1, 3, 1] [1, 3, 2]  
 [2, 1, 1] [2, 1, 2] [2, 2, 1] [2, 2, 2] [2, 3, 1] [2, 3, 2]  
 [3, 1, 1] [3, 1, 2] [3, 2, 1] [3, 2, 2] [3, 3, 1] [3, 3, 2]  
 [4, 1, 1] [4, 1, 2] [4, 2, 1] [4, 2, 2] [4, 3, 1] [4, 3, 2]

A complex N-dimensional array is stored in memory in the same way. Like complex matrices, complex arrays are stored with the entire real part first, followed by the entire imaginary part.

Every N-dimensional array has a corresponding  $N \times 1$  vector of orders that contains the sizes of each dimension of the array. This is stored with the array and can be accessed with **getorders**. The first element of the vector of orders corresponds to the slowest moving dimension, and the last element corresponds to the fastest moving dimension (refer to the [sectionnameGlossary of Terms](#) at the end of the chapter for clear definitions of these terms). The vector of orders for a  $6 \times 5 \times 4 \times 3 \times 2$  array, which has 5 dimensions, is the following  $5 \times 1$  vector:

6  
5  
4  
3  
2

Two terms that are important in working with N-dimensional arrays are “dimension index” and “dimension number.” A dimension index specifies a dimension based on indexing the vector of orders. It is a scalar, 1-to-N, where 1 corresponds to the dimension indicated by the first element of the vector of orders of the array (the slowest moving dimension) and N corresponds to the dimension indicated by the last element of the vector of orders (the fastest moving dimension).

A dimension number specifies dimensions by numbering them in the same order that one would add dimensions to an array. In other words, the dimensions of an N-dimensional array are numbered such that the fastest moving dimension has a dimension number of 1, and the slowest moving dimension has a dimension number of N.

A  $6 \times 5 \times 4 \times 3 \times 2$  array has 5 dimensions, so the first element of the vector of orders (in this case, 6) refers to the size of dimension number 5. Since the index of this element in the vector of orders is 1, the dimension index of the corresponding dimension (dimension number 5) is also 1.

You will find references to both dimension index and dimension number in the documentation for the functions that manipulate arrays.

There are a number of functions that have been designed to manipulate arrays. These functions allow you to manipulate a subarray within the array by passing in a locator vector to index any subarray that comprises a contiguous block of memory within the larger block. A vector of indices of an N-dimensional array is a  $[1\text{-to-}N] \times 1$  vector of base 1 indices into the array, where the first element corresponds to the first element in a vector of orders. An  $N \times 1$  vector of indices locates the



scalar whose position is indicated by the indices. For a  $4 \times 3 \times 2$  array  $x$ , the  $3 \times 1$  vector of indices:

3  
2  
1

indexes the  $[3,2,1]$  element of  $x$ . A  $2 \times 1$  vector of indices for this 3-dimensional example, references the 1-dimensional array whose starting location is given by the indices.

Because the elements of the vector of indices are always in the same order (the first element of the vector of indices corresponds to the slowest moving dimension of the array, the second element to the second slowest moving dimension, and so on), each unique vector of indices locates a unique subarray.

In general, an  $[N-K] \times 1$  vector of indices locates a  $K$ -dimensional subarray that begins at the position indicated by the indices. The sizes of the dimensions of the  $K$ -dimensional subarray correspond to the last  $K$  elements of the vector of orders of the  $N$ -dimensional array. For a  $6 \times 5 \times 4 \times 3 \times 2$  array  $y$ , the  $2 \times 1$  vector of indices:

2  
5

locates the  $4 \times 3 \times 2$  subarray in  $y$  that begins at  $[2,5,1,1,1]$  and ends at  $[2,5,4,3,2]$ .

## 15.1 Bracketed Indexing

Brackets ' $[ ]$ ' can be used to index  $N$ -dimensional arrays in virtually the same way that they are used to index matrices. Bracketed indexing is slower than the convenience array functions, such as **getarray** and **setarray**; however, it can be used to index non-contiguous elements. In order to index an  $N$ -dimensional array with brackets, there must be  $N$  indices located within the brackets, where the first index corresponds to the slowest moving dimension of the array and the last index corresponds to the fastest moving dimension.

For a  $2 \times 3 \times 4$  array **x**, such that

[1,1,1] through [1,3,4] =

1	2	3	4
5	6	7	8
9	10	11	12

[2,1,1] through [2,3,4] =

13	14	15	16
17	18	19	20
21	22	23	24

**x[1,2,3]** returns a  $1 \times 1 \times 1$  array containing the [1,2,3] element of **x**:

7

**x[.,3,2]** returns a  $2 \times 1 \times 1$  array containing

10

22

**x[2,.,1 4]** returns a  $1 \times 3 \times 2$  array containing

13	16
17	20
21	24

`x[:,2,1:3]` returns a  $2 \times 1 \times 3$  array containing

```

5   6   7
17  18  19

```

## 15.2 E×E Conformability

The following describes rules for E×E conformability of arrays for operators and functions with two or more arguments.

- Any N-dimensional array is conformable to a scalar.
- An array is conformable to a matrix only if the array has fewer than 3 dimensions, and the array and matrix follow the standard rules of E×E conformability.
- Two arrays are E×E conformable if they comply with one of the following requirements:
  - The two arrays have the same number of dimensions, and each dimension has the same size.
  - The two arrays have the same number of dimensions, and each of the N-2 slowest moving dimensions has the same size. In this case, the 2 fastest moving dimensions of the arrays must follow the E×E conformability rules that apply to matrices.
  - Both of the arrays have fewer than 3 dimensions, and they follow the E×E conformability rules that apply to matrices.

## 15.3 Glossary of Terms

**dimensions** The number of dimensions of an object.

**vector of orders**  $N \times 1$  vector of the sizes of the dimensions of an object, where N is the number of dimensions, and the first element corresponds to the slowest moving dimension.

**vector of indices** [1-to-N]×1 vector of indices into an array, where the first element corresponds to the first element in a vector of orders.

**dimension number** Scalar [1-to-N], where 1 corresponds to the fastest moving dimension and N to the slowest moving dimension.

**dimension index** Scalar [1-to-N], where 1 corresponds to the first element of the vector of orders or vector of indices.

**locator** [1-to-N]×1 vector of indices into an array used by array functions to locate a contiguous block of the array.

# Working with Arrays 16

## 16.1 Initializing Arrays

The use of N-dimensional arrays in **GAUSS** is an additional tool for reducing development time and increasing execution speed of programs. There are multiple ways of handling N-dimensional arrays and using them to solve problems, and these ways sometimes have implications for a trade-off between speed of execution and development time. We will try to make this clear in this chapter.

The term “arrays” specifically refers to N-dimensional arrays and must not be confused with matrices. Matrices and arrays are distinct types even if in fact they contain identical information. Functions for conversion from one to the other are described below.

There are five basic ways of creating an array depending on how the contents are specified:

- |                 |  |
|-----------------|--|
| <b>areshape</b> | Create array from specified matrix .   |
| <b>aconcat</b>  | Create array from matrices and arrays. |
| <b>aeye</b>     | Create array of identity matrices.     |

**arrayinit**     Allocate array filled with specified scalar value.

**arrayalloc**    Allocate array with no specified contents.

### 16.1.1 areshape

**areshape** is a method for creating an array with specified contents. **arrayinit** creates an array filled with a selected scalar value: **areshape** will do the same, but with a matrix. For example, given a matrix, **areshape** will create an array containing multiple copies of that matrix:

```
x = reshape(seqa(1,1,4),2,2);  
ord = 3 | 2 | 2;  
a = areshape(x,ord);  
print a;
```

```
Plane [1,...]
```

```
1.0000 2.0000  
3.0000 4.0000
```

```
Plane [2,...]
```

```
1.0000 2.0000  
3.0000 4.0000
```

```
Plane [3,...]
```

```
1.0000 2.0000  
3.0000 4.0000
```

### Reading Data from the Disk into an Array

**areshape** is a fast way to re-dimension a matrix or array already in memory. For example, suppose we have a **GAUSS** data set containing panel data and that it's small enough to be read in all at once:

---

```

panel = areshape(loadadd("panel"),5|100|10);
mn = amean(panel,2); /* 5x1x10 array of means */
                        /*of each panel */
mm = moment(panel,0); /* 5x10x10 array of moments */
                        /* of each panel */

/*
** vc is a 5x10x10 array of
** covariance matrices
**/

vc = mm / 100 - amult(atranspose(mn,1|3|2),mn);

```

**panel** is a 5×100×10 array, and in this context is 5 panels of 100 cases measured on 10 variables.

### Inserting Random Numbers into Arrays

A random array of any dimension or size can be quickly created using **areshape**. Thus, for a 10×10×5×3 array:

```

ord = { 10, 10, 5, 3 };
y = areshape(rndu(prodc(ord),1),ord);

```

The quick and dirty method above uses the linear congruential generator, which is fast but doesn't have the properties required for serious Monte Carlo work. For series simulation you will need to use the KM generator:

```

sd0 = 345678;
ord = { 10, 10, 5, 3 };
{ z,sd0 } = rndKMu(prodc(ord),1,sd0);
y = areshape(z,ord);

```

### Expanding a Matrix into an Array Vector of Matrices

For computing the log-likelihood of a variance components model of panel data, it is necessary to expand a  $T \times T$  matrix into an  $NT \times T$  array of these matrices. This is easily accomplished using **areshape**. For example:

```
m = { 1.0 0.3 0.2,  
      0.3 1.0 0.1,  
      0.2 0.1 1.0 };
```

```
r = areshape(m,3|3|3);  
print r;
```

```
Plane [1,...]
```

```
1.0000  0.3000  0.2000  
0.3000  1.0000  0.1000  
0.2000  0.1000  1.0000
```

```
Plane [2,...]
```

```
1.0000  0.3000  0.2000  
0.3000  1.0000  0.1000  
0.2000  0.1000  1.0000
```

```
Plane [3,...]
```

```
1.0000  0.3000  0.2000  
0.3000  1.0000  0.1000  
0.2000  0.1000  1.0000
```

#### 16.1.2 aconcat

**acconcat** creates arrays from conformable sets of matrices or arrays. With this function, contents are completely specified by the user. This example tries three concatenations, one along each



dimension:

```

rndseed 345678;
x1 = rndn(2,2);
x2 = arrayinit(2|2,1);

/*
** along the first dimension or rows
*/

a = aconcat(x1,x2,1);
print a;

    -0.4300 -0.2878 1.0000 1.0000
    -0.1327 -0.0573 1.0000 1.0000

/*
** along the second dimension or columns
*/

a = aconcat(x1,x2,2);
print a;

    -0.4300 -0.2878
    -0.1327 -0.0573
    1.0000  1.0000
    1.0000  1.0000

/*
** along the third dimension
*/

a = aconcat(x1,x2,3);
print a;

Plane [1,...]
```

```
-0.4300 -0.2878
-0.1327 -0.0573
```

```
Plane [2,...]
```

```
1.0000 1.0000
1.0000 1.0000
```

### 16.1.3 aeye

**aeye** creates an array in which the principal diagonal of the two trailing dimensions is set to one. For example:

```
ord = 2 | 3 | 3;
a = aeye(ord);
print a;
```

```
Plane [1,...]
```

```
1.00000 0.00000 0.00000
0.00000 1.00000 0.00000
0.00000 0.00000 1.00000
```

```
Plane [2,...]
```

```
1.00000 0.00000 0.00000
0.00000 1.00000 0.00000
0.00000 0.00000 1.00000
```

### 16.1.4 arrayinit

**arrayinit** creates an array with all elements set to a specified value. For example:

```
ord = 3 | 2 | 3;
```

```
a = arrayinit(ord,1);
print a;
```

```
Plane [1,...]
```

```
1.0000 1.0000 1.0000
1.0000 1.0000 1.0000
```

```
Plane [2,...]
```

```
1.0000 1.0000 1.0000
1.0000 1.0000 1.0000
```

```
Plane [3,...]
```

```
1.0000 1.0000 1.0000
1.0000 1.0000 1.0000
```

### 16.1.5 arrayalloc

**arrayalloc** creates an array with specified number and size of dimensions without setting elements to any values. This requires a vector specifying the order of the array. The length of the vector determines the number of dimensions, and each element determines the size of the corresponding dimensions. The array will then have to be filled using any of several methods described later in this chapter.

For example, to allocate a 2×2×3 array:

```
rndseed 345678;
ord = 3 | 2 | 2;
a = arrayalloc(ord,0);

for i(1,ord[1],1);
    a[i,...] = rndn(2,3);
endfor;
```

```
print a;

Plane [1,...]

-0.4300 -0.2878 -0.1327
-0.0573 -1.2900 0.2467

Plane [2,...]

-1.4249 -0.0796 1.2693
-0.7530 -1.7906 -0.6103

Plane [3,...]

1.2586 -0.4773 0.7044
-1.2544 0.5002 0.3559
```

The second argument in the call to **arrayalloc** specifies whether the created array is real or complex. **arrayinit** creates only real arrays.

## 16.2 Assigning to Arrays

There are three methods used for assignment to an array:

index operator	The same method as matrices, generalized to arrays.
<b>putArray</b>	Put a subarray into an N-dimensional array and returns the result.
<b>setArray</b>	Set a subarray of an N-dimensional array in place.

And there are several ways to extract parts of arrays:

index operator	The same method as matrices, generalized to arrays.
----------------	---

---

<b>getArray</b>	Get a subarray from an array.
<b>getMatrix</b>	Get a matrix from an array.
<b>getMatrix4D</b>	Get a matrix from a 4-dimensional array.
<b>getScalar3D</b>	Get a scalar from a 3-dimensional array.
<b>getScalar4D</b>	Get a scalar from a 4-dimensional array.

The index operator is the slowest way to extract parts of arrays. The specialized functions are the fastest when the circumstances are appropriate for their use.

### 16.2.1 index operator

The index operator will put a **subarray** into an array in a manner analogous to the use of index operators on matrices:

```
a = arrayinit(3|2|2,0);
b = arrayinit(3|1|2,1);
a[:,2,:] = b;
```

```
print a;
```

```
Plane [1,...]
```

```
0.000000 0.000000
1.000000 1.000000
```

```
Plane [2,...]
```

```
0.000000 0.000000
1.000000 1.000000
```

```
Plane [3,...]
```

```
0.00000 0.00000
1.0000 1.0000
```

As this example illustrates, the assignment doesn't have to be contiguous. **putMatrix** and **setMatrix** require a contiguous assignment, but for that reason they are faster.

The right hand side of the assignment can also be a matrix:

```
a[1,...] = rndn(2,2);
print a;

Plane [1,...]

-1.7906502 -0.61038103
1.2586160 -0.47736360

Plane [2,...]

0.00000 0.00000
1.00000 1.00000

Plane [3,...]

0.00000 0.00000
1.00000 1.00000
```

The index operator will extract an array from a subarray in a manner analogous to the use of index operators on matrices:

```
a = areshape(seqa(1,1,12),3|2|2);
b = a[.,1,.];

print a;

Plane [1,...]
```

```
1.0000 2.0000
3.0000 4.0000

Plane [2,...]

5.0000 6.0000
7.0000 8.0000

Plane [3,...]

9.0000 10.000

11.000 12.000

print b;

Plane [1,...]

1.0000 2.0000

Plane [2,...]

5.0000 6.0000

Plane [3,...]

9.0000 10.000
```

It is important to note that the result is always an array even if it's a scalar value:

```
c = a[1,1,1];
print c;

Plane [1,...]
```

1.0000

If you require a matrix result, and if the result has one or two dimensions, use **arraytomat** to convert to a matrix, or use **getMatrix**, **getMatrix3D**, or **getMatrix4D**. Or, if the result is a scalar, use **getScalar3D** or **getScalar4D**.

### 16.2.2 **getArray**

**getArray** is an additional method for extracting arrays:

```
a = areshape(seqa(1,1,12),3|2|2);  
b = getarray(a,2|1);  
print a;
```

Plane [1,...]

```
1.0000 2.0000  
3.0000 4.0000
```

Plane [2,...]

```
5.0000 6.0000  
7.0000 8.0000
```

Plane [3,...]

```
9.0000 10.000  
11.000 12.000
```

```
print b;
```

```
5.0000 6.0000
```

**getArray** can only extract a contiguous part of an array. To get non-contiguous parts you must use the index operator.



### 16.2.3 getMatrix

If the result is one or two dimensions, **getMatrix** returns a portion of an array converted to a matrix. **getMatrix** is about 20 percent faster than the index operator:

```
a = areshape(seqa(1,1,12),3|2|2);
b = getMatrix(a,2);
print b;

5.0000 6.0000
7.0000 8.0000
```

### 16.2.4 getMatrix4D

This is a specialized version of **getMatrix** for 4-dimensional arrays. It behaves just like **getMatrix** but is dramatically faster for that type of array. The following illustrates the difference in timing:

```
a = arrayinit(100|100|10|10,1);
t0 = date;

for i(1,100,1);
    for j(1,100,1);
        b = a[i,j,...];
    endfor;
endfor;

t1 = date;
e1 = ethsec(t0,t1);
print e1;
print;
t2=date;

for i(1,100,1);
```

```
        for j(1,100,1);
            b = getMatrix4d(a,i,j);
        endfor;
    endfor;

    t3 = date;
    e2 = ethsec(t2,t3);
    print e2;
    print;
    print ftostrC(100*((e1-e2)/e1),
        "percent difference - %6.2lf%%");

    13.0000000

    5.00000000

    percent difference - 61.54%
```

### 16.2.5 getScalar3D, getScalar4D

These are specialized versions of **getMatrix** for retrieving scalar elements of 3-dimensional and 4-dimensional arrays, respectively. They behave just like **getMatrix**, with scalar results, but are much faster. For example:

```
a = arrayinit(100|10|10,1);
t0 = date;

for i(1,100,1);
    for j(1,10,1);
        for k(1,10,1);
            b = a[i,j,k];
        endfor;
    endfor;
endfor;
```

```

t1 = date;
e1 = ethsec(t0,t1);
print e1;
print;
t2=date;

for i(1,100,1);
    for j(1,10,1);
        for k(1,10,1);
            b = getscalar3d(a,i,j,k);
        endfor;
    endfor;
endfor;

t3 = date;
e2 = ethsec(t2,t3);
print e2;
print;
print ftostrC(100*((e1-e2)/e1),
    "percent difference - %6.2lf%%");

7.00000000

2.00000000

percent difference - 71.43%

```

### 16.2.6 putArray

**putArray** enters a subarray, matrix, or scalar into an N-dimensional array and returns the result in an array. This function is much faster than the index operator, but it requires the part of the array being assigned to be contiguous:

```

a = arrayinit(3|2|2,3);
b = putarray(a,2,eye(2));

```

```
print b;

Plane [1,...]

      3.0000 3.0000
      3.0000 3.0000

Plane [2,...]

      1.0000 0.00000
      0.00000 1.0000

Plane [3,...]

      3.0000 3.0000
      3.0000 3.0000
```

### 16.2.7 setArray

**setArray** enters a subarray, matrix, or scalar into an N-dimensional array in place:

```
a = arrayinit(3|2|2,3);
setarray a,2,eye(2);
print b;

Plane [1,...]

      3.0000 3.0000
      3.0000 3.0000

Plane [2,...]

      1.0000 0.0000
      0.0000 1.0000
```

---

```
Plane [3,...]
```

```
3.0000 3.0000
3.0000 3.0000
```

## 16.3 Looping with Arrays

When working with arrays, **for** loops and **do** loops may be used in the usual way. In the following, let **Y** be an  $N \times 1 \times L$  array of  $L$  time series, **X** an  $N \times 1 \times K$  array of  $K$  independent variables, **B** a  $K \times L$  matrix of regression coefficients, **phi** a  $P \times L \times L$  array of garch coefficients, **theta** a  $Q \times L \times L$  array of arch coefficients, and **omega** a  $L \times L$  symmetric matrix of constants. The log-likelihood for a multivariate garch BEKK model can be computed using the index operator:

```
yord = getOrders(Y);
xord = getOrders(X);
gord = getOrders(phi);
aord = getOrders(theta);

N = yord[1]; /* No. of observations */
L = yord[3]; /* No. of time series */
K = xord[3]; /* No. of independent variables */
           /* in mean equation */
P = gord[1]; /* order of garch parameters */
Q = aord[1]; /* order of arch parameters */

r = maxc(P|Q);
E = Y - amult(X,areshape(B,N|K|L));
sigma = areshape(omega,N|L|L);

for i(r+1,N,1);
    for j(1,Q,1);
        W = amult(theta[j,...],
            atranspose(E[i-j,...],1|3|2));
        sigma[i,...] = sigma[i,...] + amult(W,atranspose(W,1|3|2));
```

```
        endfor;

        for j(1,P,1);
            sigma[i,...] = sigma[i,...] + amult(amult(phi[j,...],
                sigma[i-j,...]),phi[j,...]);
        endfor;
    endfor;

    sigmai = invpd(sigma);
    lndet = ln(det(sigma));
    ln1 = -0.5*( L*(N-R)*asum(ln(det(sigmai)),1) +
        asum(amult(amult(E,sigmai),atranspose(E,1|3|2)),3);
```

Instead of index operators, the above computation can be done using **getArray** and **setArray**:

```
yord = getOrders(Y);
xord = getOrders(X);
gord = getOrders(phi);
aord = getOrders(theta);

N = yord[1]; /* No. of observations */
L = yord[3]; /* No. of time series */
K = xord[3]; /* No. of independent variables */
           /* in mean equation */
P = gord[1]; /* order of garch parameters */
Q = aord[1]; /* order of arch parameters */

r = maxc(P|Q);
E = Y - amult(X,areshape(B,N|K|L));
sigma = areshape(omega,N|L|L);

for i(r+1,N,1);
    for j(1,Q,1);
        W = amult(getArray(theta,j),
            atranspose(getArray(E,i-j),2|1));
        setarray sigma,i,getArray(sigma,i)+
```

```

        amult(W,atranspose(W,2|1));
    endfor;

    for j(1,P,1);
        setarray sigma,i,toArray(sigma,i)+
            areshape(amult(amult(getArray(phi,j),
                toArray(sigma,i-j)),toArray(phi,j)),3|3);
    endfor;
endfor;

sigmai = invpd(sigma);
lndet = ln(det(sigma));
lnl = -0.5*( L*(N-R)*asum(ln(det(sigmai)),1)+
    asum(amult(amult(E,sigmai),atranspose(E,1|3|2)),3)

```

Putting the two code fragments above into loops that called them a hundred times and measuring the time, produced the following results:

index operator: 2.604 seconds

**getArray, setArray**: 1.092 seconds

Thus, the **getArray** and **setArray** methods are more than twice as fast.

### 16.3.1 loopnextindex

Several keyword functions are available in **GAUSS** for looping with arrays. The problem in the previous section, for example, can be written using these functions rather than with **for** loops:

```

sigind = r + 1;

sigloop:

```

```
sig0ind = sigind[1];
thetaind = 1;

thetaloop:
  sig0ind = sig0ind - 1;
  W = amult(getArray(theta,thetaind),
    atranspose(getArray(E,sig0ind),2|1));
  setarray sigma,sigind,getArray(sigma,sigind)+
    amult(W,atranspose(W,2|1));
  loopnextindex thetaloop,thetaind,aord;
  sig0ind = sigind;
  phiind = 1;

philoop:
  sig0ind[1] = sig0ind[1] - 1;
  setarray sigma,sigind,getArray(sigma,sigind)+
    areshape(amult(amult(getArray(phi,phiind),
      getArray(sigma,sig0ind)),
      getArray(phi,phiind)),3|3);
  loopnextindex philoop,phiind,gord;
  loopnextindex sigloop,sigind,sigord;
```

The **loopnextindex** function in this example isn't faster than the **for** loop used in the previous section primarily because the code is looping only through the first dimension in each loop. The advantages of **loopnextindex**, **previousindex**, **nextindex**, and **walkindex** are when the code is looping through the higher dimensions of a highly dimensioned array. In this case, looping through an array can be very complicated and difficult to manage using **for** loops.

**loopnextindex** can be faster and more useful.

The next example compares two ways of extracting a subarray from a 5-dimensional array:

```
ord = 3|3|3|3|3;
a = areshape(seqa(1,1,prodc(ord)),ord);
b = eye(3);

for i(1,3,1);
```



```
    for j(1,3,1);
        for k(1,3,1);
            setarray a,i|j|k,b;
        endfor;
    endfor;
endfor;

ind = { 1,1,1 };
loopi:
    setarray a,ind,b;
    loopnextindex loopi,ind,ord;
```

Calling each loop 10,000 times and measuring the time each takes, we get

**for** loop: 1.171 seconds

**loopnextindex**: .321 seconds

In other words, **loopnextindex** is about four times faster, a very significant difference.

## 16.4 Miscellaneous Array Functions

### 16.4.1 `atranspose`

This function changes the order of the dimensions. For example:

```
a = areshape(seqa(1,1,12),2|3|2);
print a;
```

```
Plane [1,...]
```

```

        1.0000 2.0000
        3.0000 4.0000
        5.0000 6.0000

Plane [2,...]

        7.0000 8.0000
        9.0000 10.000
        11.000 12.000

/*
** swap 2nd and 3rd dimension
*/

print atranspose(a,1|3|2);

Plane [1,...]

        1.0000 3.0000 5.0000
        2.0000 4.0000 6.0000

Plane [2,...]

        7.0000 9.0000 11.000
        8.0000 10.000 12.000

/*
** swap 1st and 3rd dimension
*/

print atranspose(a,3|2|1);

Plane [1,...]

        1.0000 7.0000
        3.0000 9.0000
        5.0000 11.000
```

```

Plane [2,...]

      2.0000  8.0000
      4.0000 10.000
      6.0000 12.000

/*
** move 3rd into the front
*/

print atranspose(a,3|1|2);

Plane [1,...]

      1.0000  3.0000  5.0000
      7.0000  9.0000 11.000

Plane [2,...]

      2.0000  4.0000  6.0000
      8.0000 10.000 12.000

```

## 16.4.2 amult

This function performs a matrix multiplication on the last two trailing dimensions of an array. The leading dimensions must be strictly conformable, and the last two trailing dimensions must be conformable in the matrix product sense. For example:

```

a = areshape(seqa(1,1,12),2|3|2);
b = areshape(seqa(1,1,16),2|2|4);
c = amult(a,b);
print a;

Plane [1,...]

```

```
1.0000 2.0000
3.0000 4.0000
5.0000 6.0000
```

```
Plane [2,.,.]
```

```
7.0000 8.0000
9.0000 10.000
11.000 12.000
```

```
print b;
```

```
Plane [1,.,.]
```

```
1.0000 2.0000 3.0000 4.0000
5.0000 6.0000 7.0000 8.0000
```

```
Plane [2,.,.]
```

```
9.0000 10.000 11.000 12.000
13.000 14.000 15.000 16.000
```

```
print c;
```

```
Plane [1,.,.]
```

```
11.000 14.000 17.000 20.000
23.000 30.000 37.000 44.000
35.000 46.000 57.000 68.000
```

```
Plane [2,.,.]
```

```
167.00 182.00 197.00 212.00
211.00 230.00 249.00 268.00
255.00 278.00 301.00 324.00
```

Suppose we have a matrix of data sets, a  $2 \times 2$  matrix of  $100 \times 5$  data sets that we've stored in a  $2 \times 2 \times 100 \times 5$  array called **x**. The moment matrices of these data sets can easily and quickly be computed using **atranspose** and **amult**:

```
vc = amult(atranspose(x,1|2|4|3),x);
```

### 16.4.3 amean, amin, amax

These functions compute the means, minimums, and maximums, respectively, across a dimension of an array. The size of the selected dimension of the resulting array is shrunk to one and contains the means, minimums, or maximums depending on the function called. For example:

```
a = areshape(seqa(1,1,12),2|3|2);
print a;
```

```
Plane [1,...]

    1.0000  2.0000
    3.0000  4.0000
    5.0000  6.0000

Plane [2,...]

    7.0000  8.0000
    9.0000 10.000
   11.000 12.000

/*
** compute means along third dimension
*/

print amean(a,3);

Plane [1,...]
```

```

        4.0000 5.0000
        6.0000 7.0000
        8.0000 9.0000

/*
** print means along the second dimension, i.e.,
** down the columns
*/

print amean(a,2);

    Plane [1,...]

        3.0000 4.0000

    Plane [2,...]

        9.0000 10.000

/*
** print the minimums down the columns
*/

print amin(a,2);

    Plane [1,...]

        1.0000 2.0000

    Plane [2,...]

        7.0000 8.0000

/*
** print the maximums along the third dimension
*/
```

```
print amax(a,3);  
  
Plane [1,...]  
  
7.0000 8.0000  
9.0000 10.000  
11.000 12.000
```

#### 16.4.4 getDims

This function returns the number of dimensions of an array:

```
a = arrayinit(4|4|5|2,0);  
print getdims(a);  
  
4.00
```

#### 16.4.5 getOrders

This function returns the sizes of each dimension of an array. The length of the vector returned by **getOrders** is the dimension of the array:

```
a = arrayinit(4|4|5|2,0);  
print getOrders(a);  
  
4.00  
4.00  
5.00  
2.00
```

### 16.4.6 arraytomat

This function converts an array with two or fewer dimensions to a matrix:

```
a = arrayinit(2|2,0);  
b = arraytomat(a);  
type(a);  
  
21.0000  
  
type(b);  
  
6.00000
```

### 16.4.7 mattoarray

This function converts a matrix to an array:

```
b = rndn(2,2);  
a = mattoarray(b);  
type(b);  
  
6.00000  
  
type(a);  
  
21.0000
```

## 16.5 Using Arrays with GAUSS functions

Many of the **GAUSS** functions have been re-designed to work with arrays. There are two general approaches to this implementation. There are exceptions, however, and you are urged to refer to the documentation if you are not sure how a particular **GAUSS** function handles array input.



In the first approach, the function returns an element-by-element result that is strictly conformable to the input. For example, **cdfnc** returns an array of identical size and shape to the input array:

```
a = areshape(seqa(-2,.5,12),2|3|2);
b = cdfnc(a);
```

```
print b;
```

```
Plane [1,...]
```

```
0.9772 0.9331
0.8413 0.6914
0.5000 0.3085
```

```
Plane [2,...]
```

```
0.1586 0.0668
0.0227 0.0062
0.0013 0.0002
```

In the second approach, which applies generally to **GAUSS** matrix functions, the function operates on the matrix defined by the last two trailing dimensions of the array. Thus, given a  $5 \times 10 \times 3$  array, **moment** returns a  $5 \times 3 \times 3$  array of five moment matrices computed from the five  $10 \times 3$  matrices in the input array.

Only the last two trailing dimensions matter; i.e., given a  $2 \times 3 \times 4 \times 5 \times 10 \times 6$  array, **moment** returns a  $2 \times 3 \times 4 \times 5 \times 6 \times 6$  array of moment matrices.

For example, in the following the result is a  $2 \times 3$  array of  $3 \times 1$  vectors of singular values of a  $2 \times 3$  array of  $6 \times 3$  matrices:

```
a = areshape(seqa(1,1,108),2|3|6|3);
b=svds(a);
print b;
```

Plane [1,1,...]

45.894532  
1.6407053  
1.2063156e-015

Plane [1,2,...]

118.72909  
0.63421188  
5.8652600e-015

Plane [1,3,...]

194.29063  
0.38756064  
1.7162751e-014

Plane [2,1,...]

270.30524  
0.27857175  
1.9012118e-014

Plane [2,2,...]

346.47504  
0.21732995  
1.4501098e-014

Plane [2,3,...]

422.71618  
0.17813229  
1.6612287e-014

It might be tempting to conclude from this example that, in general, a **GAUSS** function's behavior

on the last two trailing dimensions of an array is strictly analogous to the **GAUSS** function's behavior on a matrix. This may be true with some of the functions, but not all. For example, the **GAUSS meanc** function returns a column result for matrix input. However, the behavior for the **GAUSS amean** function is not analogous. This function takes a second argument that specifies on which dimension the mean is to be taken. That dimension is then collapsed to a size of 1. Thus:

```
a = areshape(seqa(1,1,24),2|3|4);
print a;
```

```
Plane [1,...]
```

```
1.000  2.000  3.000  4.000
5.000  6.000  7.000  8.000
9.000 10.000 11.000 12.000
```

```
Plane [2,...]
```

```
13.000 14.000 15.000 16.000
17.000 18.000 19.000 20.000
21.000 22.000 23.000 24.000
```

```
/*
** means computed across rows
*/
```

```
b = amean(a,1);
print b;
```

```
Plane [1,...]
```

```
2.500
6.500
10.500
```

```
Plane [2,...]
```

```
14.500
```

```
18.500
22.500

/*
** means computed down columns
*/

c = amean(a,2);
print c;

Plane [1,...]

5.000  6.000  7.000  8.000

Plane [2,...]

17.000 18.000 19.000 20.000

/*
** means computed along 3rd dimension
*/

d = amean(a,3);
print d;

Plane [1,...]

7.000  8.000  9.000 10.000
11.000 12.000 13.000 14.000
15.000 16.000 17.000 18.000
```

## 16.6 A Panel Data Model

Suppose we have  $N$  cases observed at  $T$  times. Let  $y_{it}$  be an observation on a dependent variable for the  $i^{th}$  case at time  $t$ ,  $X_{it}$  an observation of  $k$  independent variables for the  $i^{th}$  case at time  $t$ ,  $B$ , a

$K \times 1$  vector of coefficients. Then

$$y_{it} = X_{it}B + \mu_i + \epsilon_{it}$$

is a variance components model where  $\mu_i$  is a random error term uncorrelated with  $\epsilon_{it}$ , but which is correlated within cases. This implies an  $NT \times NT$  residual moment matrix that is block diagonal with  $N$   $T \times T$  moment matrices with the following form:

$$\begin{bmatrix} \sigma_\mu^2 + \sigma_\epsilon^2 & \sigma_\mu^2 & \dots & \sigma_\mu^2 \\ \sigma_\mu^2 & \sigma_\mu^2 + \sigma_\epsilon^2 & \dots & \sigma_\mu^2 \\ \vdots & \vdots & \ddots & \vdots \\ \sigma_\mu^2 & \sigma_\mu^2 & \dots & \sigma_\mu^2 + \sigma_\epsilon^2 \end{bmatrix}$$

The log-likelihood for this model is

$$\ln L = -0.5(NT \ln(2\pi) - \ln |\Omega| + (Y - XB)' \Omega^{-1} (Y - XB))$$

where  $\Omega$  is the block-diagonal moment matrix of the residuals.

## Computing the Log-likelihood

Using **GAUSS** arrays, we can compute the log-likelihood of this model without resorting to **do** loops. Let **Y** be a  $100 \times 3 \times 1$  array of observations on the dependent variable, and **X** a  $100 \times 3 \times 5$  array of observations on the independent variables. Further let **B** be a  $5 \times 1$  vector of coefficients, and **signu** and **sigc** be the residual variances of  $\mu$  and  $\epsilon$  respectively. Then, in explicit steps we compute

```
N = 100;
T = 3;
K = 5;
```

```
sigma = sigu * ones(T,T) + sige * eye(T); /* TxT sigma */
sigmai = invpd(sigma); /* sigma inverse */
lndet = N*ln(detl);
E = Y - amult(X,areshape(B,N|K|1)); /* residuals */
Omegai = areshape(sigmai,N|T|T); /* diagonal blocks */
/* stacked in a vector array */
R1 = amult(atranspose(E,1|3|2),Omegai); /* E'Omegai */
R2 = amult(R1,E); /* R1'E */
lnL = -0.5*(N*T*ln(2*pi) - lndet + asum(R2,3)); /* log-likelihood */
```

All of this can be made more efficient by nesting statements, which eliminates copying of temporary intervening arrays to local arrays. It is also useful to add a check for the positive definiteness of **sigma**:

```
N = 100;
T = 3;
K = 5;
const = -0.5*N*T*ln(2*pi);
oldt = trapchk(1);
trap 1,1;
sigmai = invpd(sigu*ones(T,T)+sige*eye(T));
trap oldt,1;

if not scalmiss(sigmai);
    E = Y - amult(X,areshape(B,N|K|1));
    lnL = const + 0.5*N*ln(detl)-
        0.5*asum(amult(amult(atranspose(E,1|3|2),
            areshape(sigmai,N|T|T)),E),3);
else;
    lnL = error(0);
endif;
```

## 16.7 Appendix

This is an incomplete list of special functions for working with arrays. Many **GAUSS** functions have been modified to handle arrays and are not listed here. For example, **cdfnc** computes the complement of the Normal cdf for each element of an array just as it would for a matrix. See the documentation for these **GAUSS** functions for information about their behavior with arrays.

<b>aconcat</b>	Concatenate conformable matrices and arrays in a user-specified dimension.
<b>aeye</b>	Create an array of identity matrices.
<b>amax</b>	Compute the maximum elements across a dimension of an array.
<b>amean</b>	Compute the mean along one dimension of an array.
<b>amin</b>	Compute the minimum elements across a dimension of an array.
<b>amult</b>	Perform a matrix multiplication on the last two trailing dimensions of an array.
<b>areshape</b>	Reshape a scalar, matrix, or array into an array of user-specified size.
<b>arrayalloc</b>	Create an N-dimensional array with unspecified contents.
<b>arrayinit</b>	Create an N-dimensional array with a specified fill value.
<b>arraytomat</b>	Change an array to type matrix.
<b>asum</b>	Compute the sum across one dimension of an array.
<b>atranspose</b>	Transpose an N-dimensional array.
<b>getarray</b>	Get a contiguous subarray from an N-dimensional array.
<b>getdims</b>	Get the number of dimensions in an array.
<b>getmatrix</b>	Get a contiguous matrix from an N-dimensional array.
<b>getmatrix4D</b>	Get a contiguous matrix from a 4-dimensional array.
<b>getorders</b>	Get the vector of orders corresponding to an array.

<b>getscalar3D</b>	Get a scalar from a 3-dimensional array.
<b>getscalar4D</b>	Get a scalar form a 4-dimensional array.
<b>loopnextindex</b>	Increment an index vector to the next logical index and jump to the specified label if the index did not wrap to the beginning.
<b>mattoarray</b>	Change a matrix to a type array.
<b>nextindex</b>	Return the index of the next element or subarray in an array.
<b>previousindex</b>	Return the index of the previous element or subarray in an array.
<b>putarray</b>	Put a contiguous subarray into an N-dimensional array and return the resulting array.
<b>setarray</b>	Set a contiguous subarray of an N-dimensional array.
<b>walkindex</b>	Walk the index of an array forward or backward through a specified dimension.



# Libraries 17

The **GAUSS** library system allows for the creation and maintenance of modular programs. The user can create “libraries” of frequently used functions that the **GAUSS** system will automatically find and compile whenever they are referenced in a program.

## 17.1 Autoloader

The autoloader resolves references to procedures, keywords, matrices, and strings that are not defined in the program from which they are referenced. The autoloader automatically locates and compiles the files containing the symbol definitions that are not resolved during the compilation of the main file. The search path used by the autoloader is first the current directory, and then the paths listed in the **src\_path** configuration variable in the order they appear. **src\_path** can be defined in the **GAUSS** configuration file.

### 17.1.1 Forward References

When the compiler encounters a symbol that has not previously been defined, that is called a “forward reference”. **GAUSS** handles forward references in two ways, depending on whether they are “left-hand side” or “right-hand side” references.

#### Left-Hand Side

A left-hand side reference is usually a reference to a symbol on the left-hand side of the equal sign in an expression.

```
x = 5;
```

Left-hand side references, since they are assignments, are assumed to be matrices. In the statement above, **x** is assumed to be a matrix and the code is compiled accordingly. If, at execution time, the expression actually returns a string, the assignment is made and the type of the symbol **x** is forced to string.

Some commands are implicit left-hand side assignments. There is an implicit left-hand side reference to **x** in each statement below:

```
clear x;  
  
load x;  
  
open x = myfile;
```

#### Right-Hand Side

A right-hand side reference is usually a reference to a symbol on the right-hand side of the equal sign in an expression such as:

```
z = 6;  
y = z + dog;  
print y;
```

In the program above, since **dog** is not previously known to the compiler, the autoloader will search for it in the active libraries. If it is found, the file containing it will be compiled. If it is not found in a library, the autoload/autodelete state will determine how it is handled.

### 17.1.2 The Autoloader Search Path

If the autoloader is OFF, no forward references are allowed. Every procedure, matrix, and string referenced by your program must be defined before it is referenced. An **external** statement can be used above the first reference to a symbol, but the definition of the symbol must be in the main file or in one of the files that are **#include**'d. No global symbols are deleted automatically.

If the autoloader is ON, **GAUSS** searches for unresolved symbol references during compilation using a specific search path as outlined below. If the autoloader is loudwordoff, an **Undefined symbol** error message will result for right-hand side references to unknown symbols.

When autoload is ON, the autodelete state controls the handling of references to unknown symbols.

The following search path will be followed to locate any symbols not previously defined:

#### Autodelete ON

1. user library
2. user-specified libraries.
3. gauss library
4. current directory, then **src\_path** for files with a **.g** extension.

Forward references are allowed and **.g** files need not be in a library. If there are symbols that cannot be found in any of the places listed above, an **Undefined symbol** error message will be

generated and all uninitialized variables and all procedures with global references will be deleted from the global symbol table. This autodeletion process is transparent to the user, since the symbols are automatically located by the autoloader the next time the program is run. This process results in more compile time, which may or may not be significant, depending on the speed of the computer and the size of the program.

### Autodelete OFF

1. user library
2. user-specified libraries.
3. gauss library

All `.g` files must be listed in a library. Forward references to symbols that are not listed in an active library are not allowed. For example:

```
x = rndn(10,10);
y = sym(x);      /* Forward reference to sym */

proc sym(x);
    retp(x+x');
endp;
```

Use an **external** statement for anything referenced above its definition if autodelete is OFF:

```
external proc sym;

x = rndn(10,10);
y = sym(x);

proc sym(x);
    retp(x+x');
endp;
```

When autodelete is OFF, symbols not found in an active library will not be added to the symbol table. This prevents the creation of uninitialized procedures in the global symbol table. No deletion of symbols from the global symbol table will take place.

## Libraries

The first place **GAUSS** looks for a symbol definition is in the “active” libraries. A **GAUSS** library is a text file that serves as a dictionary to the source files that contain the symbol definitions. When a library is active, **GAUSS** will look in it whenever it is looking for a symbol it is trying to resolve. The **library** statement is used to make a library active. Library files should be located in the subdirectory listed in the **lib\_path** configuration variable. Library files have an **.lcg** extension.

Suppose you have several procedures that are all related and you want them all defined in the same file. You can create such a file, and, with the help of a library, the autoloader will be able to find the procedures defined in that file whenever they are called.

First, create the file that is to contain your desired procedure definitions. By convention, this file is usually named with a **.src** extension, but you may use any name and any file extension. In this file, put all the definitions of related procedures you wish to use. Here is an example of such a file. It is called **norm.src**:

```
/*
** norm.src
**
** This is a file containing the definitions of three
** procedures which return the norm of a matrix x.
** The three norms calculated are the 1-norm, the
** inf-norm and the E-norm.
**/

proc onenorm(x);
    retp(maxc(sumc(abs(x)))));
endp;

proc infnorm(x);
```

```
        retp(maxc(sumc(abs(x'))));  
    endp;  
  
    proc Enorm(x);  
        retp(sumc(sumc(x.*x)));  
    endp;
```

Next, create a library file that contains the name of the file you want access to, and the list of symbols defined in it. This can be done with the **lib** command. (For details, see **lib** in the GAUSS LANGUAGE REFERENCE.)

A library file entry has a filename that is flush left. The drive and path can be included to speed up the autoloader. Indented below the filename are the symbols included in the file. There can be multiple symbols listed on a line, with spaces between. The symbol type follows the symbol name, with a colon delimiting it from the symbol name. The valid symbol types are:

<b>fn</b>	user-defined single line function.
<b>keyword</b>	keyword.
<b>proc</b>	procedure.
<b>matrix</b>	matrix, numeric or character.
<b>string</b>	string.

If the symbol type is missing, the colon must not be present and the symbol type is assumed to be **proc**. Both library files below are valid:

Example 1

```
/*  
** math  
**  
** This library lists files and procedures for mathematical routines.  
*/
```

```
norm.src
    onenorm:proc infnorm:proc Enorm:proc
complex.src
    cmmult:proc cmdiv:proc cmadd:proc cmsoln:proc
poly.src
    polychar:proc polyroot:proc polymult:proc
```

## Example 2

```
/*
** math
**
** This library lists files and procedures for mathematical routines.
*/

c:\gauss\src\norm.src
    onenorm : proc
    infnorm : proc
    Enorm : proc
c:\gauss\src\complex.src
    cmmult : proc
    cmdiv : proc
    cmadd : proc
    cmsoln : proc
c:\gauss\src\fcomp.src
    feq : proc
    fne : proc
    flt : proc
    fgt : proc
    fle : proc
    fge : proc
c:\gauss\src\fcomp.dec
    _fcmp tol : matrix
```

Once the autoloader finds, via the library, the file containing your procedure definition, everything

in that file will be compiled. For this reason, you should combine related procedures in the same file in order to minimize the compiling of procedures not needed by your program. In other words, you should not combine unrelated functions in one `.src` file because if one function in a `.src` file is needed, the whole file will be compiled.

### user Library

This is a library for user-created procedures. If the autoloader is ON, the `user` library is the first place **GAUSS** looks when trying to resolve symbol references.

You can update the `user` library with the **lib** command as follows:

```
lib user myfile.src
```

This will update the `user` library by adding a reference to `myfile.src`.

No `user` library is shipped with **GAUSS**. It will be created the first time you use the **lib** command to update it.

For details on the parameters available with the **lib** command, see the **GAUSS LANGUAGE REFERENCE**.

### .g Files

If `autoload` and `autodelete` are ON and a symbol is not found in a library, the autoloader will assume it is a procedure and look for a file that has the same name as the symbol and a `.g` extension. For example, if you have defined a procedure called **square**, you could put the definition in a file called `square.g` in one of the subdirectories listed in your **src\_path**. If `autodelete` is OFF, the `.g` file must be listed in an active library; for example, in the `user` library.



## 17.2 Global Declaration Files

If your application makes use of several global variables, create a file containing **declare** statements. Use files with the extension `.dec` to assign default values to global matrices and strings with **declare** statements. A file with a `.ext` extension containing the same symbols in **external** statements can also be created and **#include**'d at the top of any file that references these global variables. An appropriate library file should contain the name of the `.dec` files and the names of the globals they declare.

Here is an example that illustrates the way in which `.dec`, `.ext`, `.lcg` and `.src` files work together. Always begin the names of global matrices or strings with `'_'` to distinguish them from procedures.

`.src` File:

```

/*
** fcomp.src
**
** These functions use _fcmtol to fuzz the comparison operations
** to allow for roundoff error.
**
** The statement:      y = feq(a,b);
**
** is equivalent to:   y = a eq b;
**
** Returns a scalar result, 1 (true) or 0 (false)
**
**      y = feq(a,b);
**      y = fne(a,b);
**
*/

#include fcomp.ext;

proc feq(a,b);
    retp(abs(a-b) <= _fcmtol);
endp;

```

```
proc fne(a,b);  
    retp(abs(a-b) > _fcmptol);  
endp;
```

.dec File:

```
/*  
** fcomp.dec - global declaration file for fuzzy comparisons.  
*/  
  
declare matrix _fcmptol != 1e-14;
```

.ext File:

```
/*  
** fcomp.ext - external declaration file for fuzzy comparisons.  
*/  
  
external matrix _fcmptol;
```

.lcm File:

```
/*  
** fcomp.lcm - fuzzy compare library  
*/  
  
fcomp.dec  
    _fcmptol:matrix  
fcomp.src  
    feq:proc  
    fne:proc
```

With the exception of the library (.lcg) files, these files must be located along your **src\_path**. The library files must be on your **lib\_path**. With these files in place, the autoloader will be able to find everything needed to run the following programs:

```
library fcomp;
x = rndn(3,3);
xi = inv(x);
xix = xi*x;
if feq(xix,eye(3));
    print "Inverse within tolerance.";
else;
    print "Inverse not within tolerance.";
endif;
```

If the default tolerance of 1e-14 is too tight, the tolerance can be relaxed:

```
library fcomp;
x = rndn(3,3);
xi = inv(x);
xix = xi*x;
_fcmtol = 1e-12;    /* reset tolerance */
if feq(xix,eye(3));
    print "Inverse within tolerance.";
else;
    print "Inverse not within tolerance.";
endif;
```

## 17.3 Troubleshooting

Below is a partial list of errors you may encounter in using the library system, followed by the most probable cause.

**(4) : error G0290 : '/gauss/lib/prt.lcg' : Library not found**

The autoloader is looking for a library file called `prt.lcg`, because it has been activated in a **library** statement. Check the subdirectory listed in your **lib\_path** configuration variable for a file called `prt.lcg`.

**(0) : error G0292 : 'prt.dec' : File listed in library not found**

The autoloader cannot find a file called `prt.dec`. Check for this file. It should exist somewhere along your **src\_path**, if you have it listed in `prt.lcg`.

**Undefined symbols:**

**PRTVEC /gauss/src/tstprt.g(2)**

The symbol **prtvec** could not be found. Check if the file containing **prtvec** is in the **src\_path**. You may have not activated the library that contains your symbol definition. Do so in a **library** statement.

**/gauss/src/prt.dec(3) : Redefinition of '\_\_vnames' (proc)\_\_vnames being declared external matrix**

You are trying to illegally force a symbol to another type. You probably have a name conflict that needs to be resolved by renaming one of the symbols.

**/gauss/lib/prt.lcg(5) : error G0301 : 'prt.dec' : Syntax error in library**

**Undefined symbols:**

**\_\_VNAMES /gauss/src/prt.src(6)**

Check your library to see that all filenames are flush left and that all the symbols defined in that file are indented by at least one space.

### 17.3.1 Using .dec Files

Below is some advice you are encouraged to follow when constructing your own library system:

- Whenever possible, declare variables in a file that contains only **declare** statements. When your program is run again without clearing the workspace, the file containing the variable declarations will not be compiled and **declare** warnings will be prevented.
- Provide a function containing regular assignment statements to reinitialize the global variables in your program if they ever need to be reinitialized during or between runs. Put this in a separate file from the declarations:

```
proc (0) = globset;  
    _vname = "X";  
    _con = 1;  
    _row = 0;  
    _title = "";  
endp;
```

- Never declare any global in more than one file.
- To avoid meaningless redefinition errors and **declare** warnings, never declare a global more than once in any one file. Redefinition error messages and **declare** warnings are meant to help you prevent name conflicts, and will be useless to you if your code generates them normally.

By following these guidelines, any **declare** warnings and redefinition errors you get will be meaningful. By knowing that such warnings and errors are significant, you will be able to debug your programs more efficiently.



# Compiler 18

**GAUSS** allows you to compile your large, frequently used programs to a file that can be run over and over with no compile time. The compiled image is usually smaller than the uncompiled source. **GAUSS** is not a native code compiler; rather, it compiles to a form of pseudocode. The file will have a `.gcg` extension.

The **compile** command will compile an entire program to a compiled file. An attempt to edit a compiled file will cause the source code to be loaded into the editor if it is available to the system. The **run** command assumes a compiled file if no extension is given, and that a file with a `.gcg` extension is in the **src\_path**. A **saveall** command is available to save the current contents of memory in a compiled file for instant recall later. The **use** command will instantly load a compiled program or set of procedures at the beginning of an ASCII program before compiling the rest of the ASCII program file.

Since the compiled files are encoded binary files, the compiler is useful for developers who do not want to distribute their source code.

## 18.1 Compiling Programs

Programs are compiled with the **compile** command.

### 18.1.1 Compiling a File

Source code program files that can be run with the **run** command can be compiled to .gcg files with the **compile** command:

```
compile qxy.e;
```

All procedures, global matrices, arrays, strings and string arrays, and the main program segment will be saved in the compiled file. The compiled file can be run later using the **run** command. Any libraries used in the program must be present and active during the compile, but not when the program is run. If the program uses the **dlibrary** command, the .dll files must be present when the program is run and the **dlibrary** path must be set to the correct subdirectory. This will be handled automatically in your configuration file. If the program is run on a different computer than it was compiled on, the .dll files must be present in the correct location. **sysstate** (case 24) can be used to set the **dlibrary** path at run-time.

## 18.2 Saving the Current Workspace

The simplest way to create a compiled file containing a set of frequently used procedures is to use **saveall** and an **external** statement:

```
library pgraph;  
external proc xy,logx,logy,loglog,hist;  
saveall pgraph;
```

Just list the procedures you will be using in an **external** statement and follow it with a **saveall** statement. It is not necessary to list procedures that you do not explicitly call, but are called from



another procedure, because the autoloader will automatically find them before the **saveall** command is executed. Nor is it necessary to list every procedure you will be calling, unless the source will not be available when the compiled file is **use**'d.

Remember, the list of active libraries is NOT saved in the compiled file, so you may still need a **library** statement in a program that is **use**'ing a compiled file.

## 18.3 Debugging

If you are using compiled code in a development situation in which debugging is important, compile the file with line number records. After the development is over, you can recompile without line number records if the maximum possible execution speed is important. If you want to guarantee that all procedures contain line number records, put a **new** statement at the top of your program and turn line number tracking on.



# File I/O 19

The following is a partial list of the I/O commands in the **GAUSS** programming language:

<b>close</b>	Close a file.
<b>closeall</b>	Close all open files.
<b>colsf</b>	Number of columns in a file.
<b>create</b>	Create <b>GAUSS</b> data set.
<b>eof</b>	Test for end of file.
<b>fcheckerr</b>	Check error status of a file.
<b>fclearerr</b>	Check error status of a file and clear error flag.
<b>fflush</b>	Flush a file's output buffer.
<b>fgets</b>	Read a line of text from a file.
<b>fgetsa</b>	Read multiple lines of text from a file.

<b>fgetsat</b>	Read multiple lines of text from a file, discarding newlines.
<b>fgetst</b>	Read a line of text from a file, discarding newline.
<b>fileinfo</b>	Return names and information of files matching a specification.
<b>files</b>	Return a directory listing as a character matrix.
<b>filesa</b>	Return a list of files matching a specification.
<b>fopen</b>	Open a file.
<b>fputs</b>	Write strings to a file.
<b>fputst</b>	Write strings to a file, appending newlines.
<b>fseek</b>	Reposition file pointer.
<b>fstrerror</b>	Get explanation of last file I/O error.
<b>ftell</b>	Get position of file pointer.
<b>getf</b>	Load a file into a string.
<b>getname</b>	Get variable names from data set.
<b>iscplx</b>	Return whether a data set is real or complex.
<b>load</b>	Load matrix file or small ASCII file (same as <b>loadm</b> ).
<b>loadd</b>	Load a small <b>GAUSS</b> data set into a matrix.
<b>loadm</b>	Load matrix file or small ASCII file.
<b>loads</b>	Load string file.
<b>open</b>	Open a <b>GAUSS</b> data set.
<b>output</b>	Control printing to an auxiliary output file or device.
<b>readr</b>	Read a specified number of rows from a file.
<b>rowsf</b>	Number of rows in file.
<b>save</b>	Save matrices, strings, procedures.

---

<b>saved</b>	Save a matrix in a <b>GAUSS</b> data set.
<b>seekr</b>	Reset read/write pointer in a data set.
<b>sortd</b>	Sort a data set.
<b>typef</b>	Return type of data set (bytes per element).
<b>writer</b>	Write data to a data set.

## 19.1 ASCII Files

**GAUSS** has facilities for reading and writing ASCII files. Since most software can also read and write ASCII files, this provides one method of sharing data between **GAUSS** and many other kinds of programs.

### 19.1.1 Matrix Data

#### Reading

Files containing numeric data that are delimited with spaces or commas and are small enough to fit into a single matrix or string can be read with **load**. Larger ASCII data files can be converted to **GAUSS** data sets with the ATOG utility program (see ATOG, Chapter 23). ATOG can convert packed ASCII files as well as delimited files.

For small delimited data files, the **load** statement can be used to load the data directly into a **GAUSS** matrix. The resulting **GAUSS** matrix must be no larger than the limit for a single matrix.

For example,

```
load x[] = dat1.asc;
```

will load the data in the file `dat1.asc` into an  $N \times 1$  matrix **x**. This method is preferred because **rows(x)** can be used to determine how many elements were actually loaded, and the matrix can be **reshape**'d to the desired form:

```
load x[] = dat1.asc;
if rows(x) eq 500;
    x = reshape(x,100,5);
else;
    errorlog "Read Error";
end;
endif;
```

For quick interactive loading without error checking, use

```
load x[100,5] = dat1.asc;
```

This will load the data into a 100×5 matrix. If there are more or fewer than 500 numbers in the data set, the matrix will automatically be reshaped to 100×5.

### Writing

To write data to an ASCII file the **print** or **printfm** command is used to print to the auxiliary output. The resulting files are standard ASCII files and can be edited with **GAUSS**'s editor or another text editor.

The **output** and **outwidth** commands are used to control the auxiliary output. The **print** or **printfm** command is used to control what is sent to the output file.

The window can be turned on and off using **screen**. When printing a large amount of data to the auxiliary output, the window can be turned off using the command

```
screen off;
```

This will make the process much faster, especially if the auxiliary output is a disk file.

It is easy to forget to turn the window on again. Use the **end** statement to terminate your programs; **end** will automatically perform **screen on** and **output off**.

The following commands can be used to control printing to the auxiliary output:

---

<b>format</b>	Specify format for printing a matrix.
<b>output</b>	Open, close, rename auxiliary output file or device.
<b>outwidth</b>	Set auxiliary output width.
<b>printfm</b>	Formatted matrix print.
<b>print</b>	Print matrix or string.
<b>screen</b>	Turn printing to the window on and off.

This example illustrates printing a matrix to a file:

```
format /rd 8,2;
outwidth 132;
output file = myfile.asc reset;
screen off;
print x;
output off;
screen on;
```

The numbers in the matrix **x** will be printed with a field width of 8 spaces per number, and with 2 places beyond the decimal point. The resulting file will be an ASCII data file. It will have 132 column lines maximum.

A more extended example follows. This program will write the contents of the **GAUSS** file **mydata.dat** into an ASCII file called **mydata.asc**. If there is an existing file by the name of **mydata.asc**, it will be overwritten:

```
output file = mydata.asc reset;
screen off;
format /rd 1,8;
open fp = mydata;
do until eof(fp);
    print readr(fp,200);;
```

```
endo;  
fp = close(fp);  
end;
```

The **output ... reset** command will create an auxiliary output file called `mydata.asc` to receive the output. The window is turned off to speed up the process. The **GAUSS** data file `mydata.dat` is opened for reading and 200 rows are read per iteration until the end of the file is reached. The data read are printed to the auxiliary output `mydata.asc` only, because the window is off.

### 19.1.2 General File I/O

**getf** will read a file and return it in a string variable. Any kind of file can be read in this way as long as it will fit into a single string variable.

To read files sequentially, use **fopen** to open the file and use **fgets**, **fputs**, and associated functions to read and write the file. The current position in a file can be determined with **ftell**. The following example uses these functions to copy an ASCII text file:

```
proc copy(src, dest);  
    local fin, fout, str;  
  
    fin = fopen(src, "rb");  
    if not fin;  
        retp(1);  
    endif;  
  
    fout = fopen(dest, "wb");  
    if not fin;  
        call close(fin);  
        retp(2);  
    endif;  
  
    do until eof(fin);
```



```

        str = fgets(fin, 1024);
        if fputs(fout, str) /= 1;
            call close(fin);
            call close(fout);
            retp(3);
        endif;
    endo;

    call close(fin);
    call close(fout);
    retp(0);
endp;

```

## 19.2 Data Sets

**GAUSS** data sets are the preferred method of storing data contained in a single matrix for use within **GAUSS**. Use of these data sets allows extremely fast reading and writing of data. Many library functions are designed to read data from these data sets.

If you want to store multiple variables of various types in a single file, see **GAUSS DATA ARCHIVES**, Section 19.3.

### 19.2.1 Layout

**GAUSS** data sets are arranged as matrices; that is, they are organized in terms of rows and columns. The columns in a data file are assigned names, and these names are stored in the header, or, in the case of the **v89** format, in a separate header file.

The limit on the number of rows in a **GAUSS** data set is determined by disk size. The limit on the number of columns is limited by RAM. Data can be stored in 2, 4, or 8 bytes per number, rather than just 8 bytes as in the case of **GAUSS** matrix files.

The ranges of the different formats are:

Bytes	Type	Significant Digits	Range
2	integer	4	$-32768 \leq X \leq 32767$
4	single	6-7	$8.43\text{E-}37 \leq  X  \leq 3.37\text{E+}38$
8	double	15-16	$4.19\text{E-}307 \leq  X  \leq 1.67\text{E+}308$

### 19.2.2 Creating Data Sets

Data sets can be created with the **create** or **datacreate** command. The names of the columns, the type of data, etc., can be specified. (For details, see **create** in the GAUSS LANGUAGE REFERENCE.)

Data sets, unlike matrices, cannot change from real to complex, or vice-versa. Data sets are always stored a row at a time. The rows of a complex data set, then, have the real and imaginary parts interleaved, element by element. For this reason, you cannot write rows from a complex matrix to a real data set—there is no way to interleave the data without rewriting the entire data set. If you must, explicitly convert the rows of data first, using the **real** and **imag** functions (see the GAUSS LANGUAGE REFERENCE), and then write them to the data set. Rows from a real matrix CAN be written to a complex data set; **GAUSS** simply supplies 0's for the imaginary part.

To create a complex data set, include the **complex** flag in your **create** command.

### 19.2.3 Reading and Writing

The basic functions in **GAUSS** for reading data files are **open** and **readr**:

```
open f1 = dat1;  
x = readr(f1,100);
```

The call to **readr** in this example will read in 100 rows from `dat1.dat`. The data will be assigned to a matrix **x**.

**loadd** and **saved** can be used for loading and saving small data sets.

The following example illustrates the creation of a **GAUSS** data file by merging (horizontally concatenating) two existing data sets:

```
file1 = "dat1";
file2 = "dat2";
outfile = "daty";
open fin1 = ^file1 for read;
open fin2 = ^file2 for read;
varnames = getname(file1)|getname(file2);
otyp = maxc(typef(fin1)|typef(fin2));
create fout = ^outfile with ^varnames,0,otyp;
nr = 400;
do until eof(fin1) or eof(fin2);
    y1 = readr(fin1,nr);
    y2 = readr(fin2,nr);
    r = maxc(rows(y1)|rows(y2));
    y = y1[1:r,.] ~ y2[1:r,];
    call writer(fout,y);
end;
closeall fin1,fin2,fout;
```

In this example, data sets `dat1.dat` and `dat2.dat` are opened for reading. The variable names from each data set are read using **getname**, and combined in a single vector called **varnames**. A variable called **otyp** is created, which will be equal to the larger of the two data types of the input files. This will insure that the output is not rounded to less precision than the input files. A new data set `daty.dat` is created using the **create ... with ...** command. Then, on every iteration of the loop, 400 rows are read in from each of the two input data sets, horizontally concatenated, and written out to `daty.dat`. When the end of one of the input files is reached, reading and writing will stop. The **closeall** command is used to close all files.

### 19.2.4 Distinguishing Character and Numeric Data

Although **GAUSS** itself does not distinguish between numeric and character columns in a matrix or data set, some of the **GAUSS** Application programs do. When creating a data set, it is important to indicate the type of data in the various columns. The following discusses two ways of doing this.

## Using Type Vectors

The **v89** data set format distinguished between character and numeric data in data sets by the case of the variable names associated with the columns. The **v96** data set format, however, stores this type information separately, resulting in a much cleaner and more robust method of tracking variable types, and greater freedom in the naming of data set variables.

When you create a data set, you can supply a vector indicating the type of data in each column of the data set. For example:

```
data = { M 32  21500,
         F 27  36000,
         F 28  19500,
         M 25  32000 };
vnames = { "Sex" "Age" "Pay" };
vtypes = { 0 1 1 };
create f = mydata with ^vnames, 3, 8, vtypes;
call writer(f,data);
f = close(f);
```

To retrieve the type vector, use **vartypef**.

```
open f = mydata for read;
vn = getnamef(f);
vt = vartypef(f);
print vn';
print vt';
```

Sex	Age	Pay
0	1	1

The call to **getnamef** in this example returns a string array rather than a character vector, so you can print it without the '\$' prefix.

---

## Using the Uppercase/Lowercase Convention (v89 Data Sets)

Historically, some **GAUSS** Application programs recognized an “uppercase/lowercase” convention: if the variable name was uppercase, the variable was assumed to be numeric, and if it was lowercase, the variable was assumed to be character.

However, this is now obsolete; use **vartypef** and **v96** data sets to be compatible with future versions.

## 19.3 GAUSS Data Archives

The **GAUSS** Data Archive (GDA) is extremely powerful and flexible, giving you much greater control over how you store your data. There is no limitation on the number of variables that can be stored in a GDA, and the only size limitation is the amount of available disk space. Moreover, GDA's are designed to hold whatever type of data you want to store in them. You may write matrices, arrays, strings and string arrays to a GDA, and the GDA will keep track of the type, size and location of each of the variables contained in it.

See Section [19.5.12](#) for information on the layout of a GDA.

### 19.3.1 Creating and Writing Variables to GDA's

To create a **GAUSS** Data Archive, call **gdaCreate**, which creates a GDA containing only header information. It is recommended that file names passed into **gdaCreate** have a **.gda** extension; however, **gdaCreate** will not force an extension.

To write variables to the GDA, you must call **gdaWrite**. A single call to **gdaWrite** writes only one variable to the GDA. Writing multiple variables requires multiple calls to **gdaWrite**.

For example, the following code:

```
ret = gdaCreate("myfile.gda",1);  
ret = gdaWrite("myfile.gda",rndn(100,50),"x1");
```

```
ret = gdaWrite("myfile.gda","This is a string","str1");  
ret = gdaWrite("myfile.gda",394,"x2");
```

produces a GDA containing the following variables:

Index	Name	Type	Size
1	x1	matrix	100 × 50
2	str1	string	16 chars
3	x2	matrix	1 × 1

### 19.3.2 Reading Variables from GDA's

To read a variable from a **GAUSS** Data Archive, you may call either **gdaRead** or **gdaReadByIndex**. **gdaRead** takes a variable name and returns the variable data. **gdaReadByIndex** returns the variable data for a specified variable index.

For example, to get the variable **x1** out of `myfile.gda`, you could call:

```
y = gdaRead("myfile.gda","x1");
```

or

```
y = gdaReadByIndex("myfile.gda",1);
```

If you want to read only a part of a variable in a GDA, call **gdaReadSome**.

### 19.3.3 Updating Variables in GDA's

To overwrite an entire variable in a GDA, you may call **gdaUpdate** or **gdaUpdateAndPack**. If the new variable is not the same size as the variable that it is replacing, **gdaUpdate** will leave empty

bytes in the file, while **gdaUpdateAndPack** will pack the file (from the location of the variable that is being replaced to the end of the file) to remove those empty bytes.

**gdaUpdate** is usually faster, since it does not move data in the file unnecessarily. However, calling **gdaUpdate** several times for one file may result in a file with a large number of empty bytes.

On the other hand, **gdaUpdateAndPack** uses disk space efficiently, but it may be slow for large files (especially if the variable to be updated is one of the first variables in the file).

If speed and disk space are both concerns and you are going to update several variables, it will be most efficient to use **gdaUpdate** to update the variables and then call **gdaPack** once at the end to pack the file.

The syntax is the same for both **gdaUpdate** and **gdaUpdateAndPack**:

```
ret = gdaUpdate("myfile.gda",rndn(1000,100),"x1");
```

```
ret = gdaUpdateAndPack("myfile.gda",rndn(1000,100),"x1");
```

To overwrite part of a variable in a GDA, call **gdaWriteSome**.

## 19.4 Matrix Files

**GAUSS** matrix files are files created by the **save** command.

The **save** command takes a matrix in memory, adds a header that contains information on the number of rows and columns in the matrix, and stores it on disk. Numbers are stored in double precision just as they are in matrices in memory. These files have the extension **.fmt**.

Matrix files can be no larger than a single matrix. No variable names are associated with matrix files.

**GAUSS** matrix files can be **load**'ed into memory using the **load** or **loadm** command or they can be opened with the **open** command and read with the **readr** command. With the **readr** command, a subset of the rows can be read. With the **load** command, the entire matrix is **load**'ed.

**GAUSS** matrix files can be **open**'ed **for read**, but not **for append**, or **for update**.

If a matrix file has been opened and assigned a file handle, **rowsf** and **colsf** can be used to determine how many rows and columns it has without actually reading it into memory. **seekr** and **readr** can be used to jump to particular rows and to read them into memory. This is useful when only a subset of rows is needed at any time. This procedure will save memory and be much faster than **load**'ing the entire matrix into memory.

## 19.5 File Formats

This section discusses the **GAUSS** binary file formats.

There are four currently supported matrix file formats:

Version	Extension	Support
<b>Small Matrix v89</b>	.fmt	Obsolete, use <b>v96</b> .
<b>Extended Matrix v89</b>	.fmt	Obsolete, use <b>v96</b> .
<b>Matrix v92</b>	.fmt	Obsolete, use <b>v96</b> .
<b>Universal Matrix v96</b>	.fmt	Supported for read/write.

There are four currently supported string file formats:

Version	Extension	Support
<b>Small String v89</b>	.fst	Obsolete, use <b>v96</b> .
<b>Extended String v89</b>	.fst	Obsolete, use <b>v96</b> .
<b>String v92</b>	.fst	Obsolete, use <b>v96</b> .
<b>Universal String v96</b>	.fst	Supported for read/write.

There are four currently supported data set formats:



Version	Extension	Support
Small Data Set v89	.dat, .dht	Obsolete, use <b>v96</b> .
Extended Data Set v89	.dat, .dht	Obsolete, use <b>v96</b> .
Data Set v92	.dat	Obsolete, use <b>v96</b> .
Universal Data Set v96	.dat	Supported for read/write.

19.5.1 Small Matrix v89 (Obsolete)

Matrix files are binary files, and cannot be read with a text editor. They are created with **save**. Matrix files with up to 8190 elements have a `.fmt` extension and a 16-byte header formatted as follows:

Offset	Description
0-1	DDDD hex, identification flag
2-3	rows, unsigned 2-byte integer
4-5	columns, unsigned 2-byte integer
6-7	size of file minus 16-byte header, unsigned 2-byte integer
8-9	type of file, 0086 hex for real matrices, 8086 hex for complex matrices
10-15	reserved, all 0's

The body of the file starts at offset 16 and consists of IEEE format double precision floating point numbers or character elements of up to 8 characters. Character elements take up 8 bytes and are padded on the right with zeros. The size of the body of the file is 8\*rows\*cols rounded up to the next 16-byte paragraph boundary. Numbers are stored row by row. A 2×3 real matrix will be stored on disk in the following way, from the lowest addressed element to the highest addressed element:

[1, 1] [1, 2] [1, 3] [2, 1] [2, 2] [2, 3]

For complex matrices, the size of the body of the file is 16\*rows\*cols. The entire real part of the matrix is stored first, then the entire imaginary part. A 2×3 complex matrix will be stored on disk

in the following way, from the lowest addressed element to the highest addressed element:

<i>(real part)</i>	[1, 1]	[1, 2]	[1, 3]	[2, 1]	[2, 2]	[2, 3]
<i>(imaginary part)</i>	[1, 1]	[1, 2]	[1, 3]	[2, 1]	[2, 2]	[2, 3]

### 19.5.2 Extended Matrix v89 (Obsolete)

Matrices with more than 8190 elements are saved in an extended format. These files have a 16-byte header formatted as follows:

Offset	Description
0-1	EEDD hex, identification flag
2-3	type of file, 0086 hex for real matrices, 8086 hex for complex matrices
4-7	rows, unsigned 4-byte integer
8-11	columns, unsigned 4-byte integer
12-15	size of file minus 16-byte header, unsigned 4-byte integer

The size of the body of an extended matrix file is 8\*rows\*cols (not rounded up to a paragraph boundary). Aside from this, the body is the same as the small matrix **v89** file.

### 19.5.3 Small String v89 (Obsolete)

String files are created with **save**. String files with up to 65519 characters have a 16-byte header formatted as follows:

Offset	Description
0-1	DFDF hex, identification flag
2-3	1, unsigned 2-byte integer
4-5	length of string plus null byte, unsigned 2-byte integer
6-7	size of file minus 16-byte header, unsigned 2-byte integer
8-9	001D hex, type of file
10-15	reserved, all 0's

The body of the file starts at offset 16. It consists of the string terminated with a null byte. The size of the file is the 16-byte header plus the length of the string and null byte rounded up to the next 16-byte paragraph boundary.

19.5.4 Extended String v89 (Obsolete)

Strings with more than 65519 characters are saved in an extended format. These files have a 16-byte header formatted as follows:

Offset	Description
0-1	EEDF hex, identification flag
2-3	001D hex, type of file
4-7	1, unsigned 4-byte integer
8-11	length of string plus null byte, unsigned 4-byte integer
12-15	size of file minus 16-byte header, unsigned 4-byte integer

The body of the file starts at offset 16. It consists of the string terminated with a null byte. The size of the file is the 16-byte header plus the length of the string and null byte rounded up to the next 8-byte boundary.

19.5.5 Small Data Set v89 (Obsolete)

All data sets are created with **create**. **v89** data sets consist of two files; one **.dht** contains the header information; the second (**.dat**) contains the binary data. The data will be one of three types:

- 8-byte IEEE floating point
- 4-byte IEEE floating point
- 2-byte signed binary integer, twos complement

Numbers are stored row by row.

The `.dht` file is used in conjunction with the `.dat` file as a descriptor file and as a place to store names for the columns in the `.dat` file. Data sets with up to 8175 columns have a `.dht` file formatted as follows:

Offset	Description
0-1	DADA hex, identification flag
2-5	reserved, all 0's
6-7	columns, unsigned 2-byte integer
8-9	row size in bytes, unsigned 2-byte integer
10-11	header size in bytes, unsigned 2-byte integer
12-13	data type in <code>.dat</code> file (2 4 8), unsigned 2-byte integer
14-17	reserved, all 0's
18-21	reserved, all 0's
22-23	control flags, unsigned 2-byte integer
24-127	reserved, all 0's

Column names begin at offset 128 and are stored 8 bytes each in ASCII format. Names with less than 8 characters are padded on the right with bytes of 0.

The number of rows in the `.dat` file is calculated in **GAUSS** using the file size, columns, and data type. This means that users can modify the `.dat` file by adding or deleting rows with other software without updating the header information.

Names for the columns should be lowercase for character data, to be able to distinguish them from numeric data with **vartype**.

**GAUSS** currently examines only the 4's bit of the control flags. This bit is set to 0 for real data sets, 1 for complex data sets. All other bits are 0.

Data sets are always stored a row at a time. A real data set with 2 rows and 3 columns will be stored on disk in the following way, from the lowest addressed element to the highest addressed element:

```
[1, 1] [1, 2] [1, 3]
[2, 1] [2, 2] [2, 3]
```

The rows of a complex data set are stored with the real and imaginary parts interleaved, element by element. A 2×3 complex data set, then, will be stored on disk in the following way, from the lowest addressed element to the highest addressed element:

```
[1, 1]r [1, 1]i [1, 2]r [1, 2]i [1, 3]r [1, 3]i
[2, 1]r [2, 1]i [2, 2]r [2, 2]i [2, 3]r [2, 3]i
```

19.5.6 Extended Data Set v89 (Obsolete)

Data sets with more than 8175 columns are saved in an extended format that cannot be read by the 16-bit version. These files have a .dht descriptor file formatted as follows:

Offset	Description
0-1	EEDA hex, identification flag
2-3	data type in .dat file (2 4 8), unsigned 2-byte integer
4-7	reserved, all 0's
8-11	columns, unsigned 4-byte integer
12-15	row size in bytes, unsigned 4-byte integer
16-19	header size in bytes, unsigned 4-byte integer
20-23	reserved, all 0's
24-27	reserved, all 0's
28-29	control flags, unsigned 2-byte integer
30-127	reserved, all 0's

Aside from the differences in the descriptor file and the number of columns allowed in the data file, extended data sets conform to the **v89** data set description specified above.

19.5.7 Matrix v92 (Obsolete)

Offset	Description
0-3	always 0
4-7	always 0xEECDCDCD

Offset	Description
8-11	reserved
12-15	reserved
16-19	reserved
20-23	0 - real matrix, 1 - complex matrix
24-27	number of dimensions
	0 - scalar
	1 - row vector
	2 - column vector, matrix
28-31	header size, 128 + number of dimensions * 4, padded to 8-byte boundary
32-127	reserved

If the data is a scalar, the data will directly follow the header.

If the data is a row vector, an unsigned integer equaling the number of columns in the vector will precede the data, along with 4 padding bytes.

If the data is a column vector or a matrix, there will be two unsigned integers preceding the data. The first will represent the number of rows in the matrix and the second will represent the number of columns.

The data area always begins on an even 8-byte boundary. Numbers are stored in double precision (8 bytes per element, 16 if complex). For complex matrices, all of the real parts are stored first, followed by all the imaginary parts.

### 19.5.8 String v92 (Obsolete)

Offset	Description
0-3	always 0
4-7	always 0xEECFCFCF
8-11	reserved
12-15	reserved
16-19	reserved

Offset	Description
20-23	size of string in units of 8 bytes
24-27	length of string plus null terminator in bytes
28-127	reserved

The size of the data area is always divisible by 8, and is padded with nulls if the length of the string is not evenly divisible by 8. If the length of the string is evenly divisible by 8, the data area will be the length of the string plus 8. The data area follows immediately after the 128-byte header.

### 19.5.9 Data Set v92 (Obsolete)

Offset	Description
0-3	always 0
4-7	always 0xEECACACA
8-11	reserved
12-15	reserved
16-19	reserved
20-23	rows in data set
24-27	columns in data set
28-31	0 - real data set, 1 - complex data set
32-35	type of data in data set, 2, 4, or 8
36-39	header size in bytes is $128 + \text{columns} * 9$
40-127	reserved

The variable names begin at offset 128 and are stored 8 bytes each in ASCII format. Each name corresponds to one column of data. Names less than 8 characters are padded on the right with bytes of zero.

The variable type flags immediately follow the variable names. They are 1-byte binary integers, one per column, padded to an even 8-byte boundary. A 1 indicates a numeric variable and a 0 indicates a character variable.

The contents of the data set follow the header and start on an 8-byte boundary. Data is either 2-byte signed integer, 4-byte single precision floating point or 8-byte double precision floating point.

**19.5.10 Matrix v96**

Offset	Description
0-3	always 0xFFFFFFFF
4-7	always 0
8-11	always 0xFFFFFFFF
12-15	always 0
16-19	always 0xFFFFFFFF
20-23	0xFFFFFFFF for forward byte order, 0 for backward byte order
24-27	0xFFFFFFFF for forward bit order, 0 for backward bit order
28-31	always 0xABCDEF01
32-35	currently 1
36-39	reserved
40-43	floating point type, 1 for IEEE 754
44-47	1008 (double precision data)
48-51	8, the size in bytes of a double matrix
52-55	0 - real matrix, 1 - complex matrix
56-59	1 - imaginary part of matrix follows real part (standard <b>GAUSS</b> style) 2 - imaginary part of each element immediately follows real part (FORTRAN style)
60-63	number of dimensions 0 - scalar 1 - row vector 2 - column vector or matrix
64-67	1 - row major ordering of elements, 2 - column major
68-71	always 0
72-75	header size, 128 + dimensions * 4, padded to 8-byte boundary
76-127	reserved

If the data is a scalar, the data will directly follow the header.

If the data is a row vector, an unsigned integer equaling the number of columns in the vector will precede the data, along with 4 padding bytes.

If the data is a column vector or a matrix, there will be two unsigned integers preceding the data. The first will represent the number of rows in the matrix and the second will represent the number



of columns.

The data area always begins on an even 8-byte boundary. Numbers are stored in double precision (8 bytes per element, 16 if complex). For complex matrices, all of the real parts are stored first, followed by all the imaginary parts.

### 19.5.11 Data Set v96

Offset	Description
0-3	always 0xFFFFFFFF
4-7	always 0
8-11	always 0xFFFFFFFF
12-15	always 0
16-19	always 0xFFFFFFFF
20-23	0xFFFFFFFF for forward byte order, 0 for backward byte order
24-27	0xFFFFFFFF for forward bit order, 0 for backward bit order
28-31	0xABCDEF02
32-35	version, currently 1
36-39	reserved
40-43	floating point type, 1 for IEEE 754
44-47	12 - signed 2-byte integer 1004 - single precision floating point 1008 - double precision float
48-51	2, 4, or 8, the size of an element in bytes
52-55	0 - real matrix, 1 - complex matrix
56-59	1 - imaginary part of matrix follows real part (standard <b>GAUSS</b> style) 2 - imaginary part of each element immediately follows real part (FORTRAN style)
60-63	always 2
64-67	1 for row major ordering of elements, 2 for column major
68-71	always 0
72-75	header size, 128 + columns * 33, padded to 8-byte boundary
76-79	reserved

Offset	Description
80-83	rows in data set
84-87	columns in data set
88-127	reserved

The variable names begin at offset 128 and are stored 32 bytes each in ASCII format. Each name corresponds to one column of data. Names less than 32 characters are padded on the right with bytes of zero.

The variable type flags immediately follow the variable names. They are 1-byte binary integers, one per column, padded to an even 8-byte boundary. A 1 indicates a numeric variable and a 0 indicates a character variable.

Contents of the data set follow the header and start on an 8-byte boundary. Data is either 2-byte signed integer, 4-byte single precision floating point or 8-byte double precision floating point.

### 19.5.12 GAUSS Data Archive

A **GAUSS** Data Archive consists of a header, followed by the variable data and, finally, an array of variable descriptors containing information about each variable.

#### Header

The header for a **GAUSS** Data Archive is laid out as follows:

Offset	Type	Description
0-3	32-bit unsigned integer	always 0xFFFFFFFF
4-7	32-bit unsigned integer	always 0
8-11	32-bit unsigned integer	always 0xFFFFFFFF
12-15	32-bit unsigned integer	always 0
16-19	32-bit unsigned integer	always 0xFFFFFFFF
20-23	32-bit unsigned integer	0xFFFFFFFF for forward byte order, 0 for backward byte order
24-27	32-bit unsigned integer	always 0

Offset	Type	Description
28-31	32-bit unsigned integer	always 0xABCDEF08
32-35	32-bit unsigned integer	version, currently 1
36-39	32-bit unsigned integer	reserved
40-43	32-bit unsigned integer	floating point type, 1 for IEEE 754
44-55	32-bit unsigned integers	reserved
56-63	64-bit unsigned integer	number of variables
64-67	32-bit unsigned integer	header size, 128
68-95	32-bit unsigned integers	reserved
96-103	64-bit unsigned integer	offset of variable descriptor table from end of header
104-127	64-bit unsigned integers	reserved

Variable Data

After the header comes the variable data. Matrices are laid out in row-major order, and strings are written with a null-terminating byte.

For string arrays, the string array data is written out first in row-major order with each element null terminated. The data is followed by an array of *rows*×*columns* struct **satable**’s. A struct **satable** consists of two members:

Member	Type	Description
off	<b>size_t</b>	offset of element data from beginning of string array data
len	<b>size_t</b>	length of element data, including null-terminating byte

On a 32-bit machine, a **size\_t** is 4 bytes. On a 64-bit machine, it is 8 bytes.

Arrays are written with the orders (sizes) of each dimension followed by the array data. For example, the following 2×3×4 array:

[1,1,1] through [1,3,4] =

1	2	3	4
5	6	7	8
9	10	11	12

[2,1,1] through [2,3,4] =

```
13 14 15 16
17 18 19 20
21 22 23 24
```

would be written out like this:

```
1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24
```

## Variable Structures

The variable data is followed by an array of variable descriptors. For each variable in the GDA, there is a corresponding variable descriptor in this array. A variable descriptor is laid out as follows:

Offset	Type	Description
0-3	32-bit unsigned integer	variable type
4-7	32-bit unsigned integer	data type, 10 for 8 byte floating point
8-11	32-bit unsigned integer	dimensions, used only for arrays
12-15	32-bit unsigned integer	complex flag, 1 for real data, 0 for complex
16-19	32-bit unsigned integer	size of pointer, indicates whether the variable was written on a 32-bit or 64-bit platform
20-23	32-bit unsigned integer	huge flag, indicates whether the variable is larger than INT_MAX
24-31	64-bit unsigned integer	rows for matrices and string arrays
32-39	64-bit unsigned integer	columns for matrices and string arrays, length for strings, including null-terminating byte
40-47	64-bit unsigned integer	index of the variable in the GDA
48-55	64-bit unsigned integer	offset of variable data from end of header
56-63	64-bit unsigned integer	length of variable data in bytes
64-143	string	name of variable, null-terminated

The variable type (bytes 0-3) may be any of the following:

- 
- 20** array
  - 30** matrix
  - 40** string
  - 50** string array

The size of pointer element (bytes 16-19) is the size of a pointer on the machine on which the variable was written to the GDA. It will be set to 4 on 32-bit machines and 8 on 64-bit machines. This element is used only for string array variables. If a GDA containing string arrays is created on a 32-bit machine and then read on a 64-bit machine, or vice versa, then the size of pointer element indicates how the members of the struct **satable**'s must be converted in order to be read on the current machine.

The huge flag (bytes 20-23) is set to 1 if the variable size is greater than INT\_MAX, which is defined as 2147483647. A variable for which the huge flag is set to 1 may not be read into **GAUSS** on a 32-bit machine.

The variable index element (bytes 40-47) contains the index of the variable in the GDA. Although the variable data is not necessarily ordered by index (see **gdaUpdate**), the variable descriptors are. Therefore, the indices are always in ascending order.



# Foreign Language Interface 20

The Foreign Language Interface (FLI) allows users to create functions written in C, FORTRAN, or other languages, and call them from a **GAUSS** program. The functions are placed in dynamic libraries (DLLs, also known as shared libraries or shared objects) and linked in at run-time as needed. The FLI functions are:

**dlibrary**      Link and unlink dynamic libraries at run-time.

**dllcall**      Call functions located in dynamic libraries.

**GAUSS** recognizes a default dynamic library directory, a directory where it will look for your dynamic-link libraries when you call **dlibrary**. You can specify the default directory in `gauss.cfg` by setting **dlib\_path**. As it is shipped, `gauss.cfg` specifies `$(GAUSSDIR)/dlib` as the default directory.

## 20.1 Writing FLI Functions

Your FLI functions should be written to the following specifications:

1. Take 0 or more pointers to doubles as arguments.

This does not mean you cannot pass strings to an FLI function. Just recast the double pointer to a char pointer inside the function.

2. Take those arguments either in a list or a vector.
3. Return an integer.

In C syntax, then, your functions would take one of the following forms:

1. `int func(void);`
2. `int func(double *arg1 [],double *arg2,...);`
3. `int func(double *arg[]);`

Functions can be written to take a list of up to 100 arguments, or a vector (in C terms, a 1-dimensional array) of up to 1000 arguments. This does not affect how the function is called from **GAUSS**; the **dllcall** statement will always appear to pass the arguments in a list. That is, the **dllcall** statement will always look as follows:

```
dllcall func(a,b,c,d[],e...);
```

For details on calling your function, passing arguments to it, getting data back, and what the return value means, see **dllcall** in the **GAUSS LANGUAGE REFERENCE**.



## 20.2 Creating Dynamic Libraries

The following describes how to build a dynamic library called `hyp.dll` (on Windows) or `libhyp.so` (on UNIX/Linux) from the source file `hyp.c`.

As mentioned in the previous section, your FLI functions may take only pointers to doubles as arguments. Therefore, you should define your FLI functions to be merely wrapper functions that cast their arguments as necessary and then call the functions that actually do the work. This is demonstrated in the source file `hyp.c`:

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>

/* This code is not meant to be efficient. It is meant
** to demonstrate the use of the FLI.
*/

/* this does all the work, not exported */
static int hypo(double *x, double *y, double *h, int r, int c)
{
    double *wx;
    double *wy;
    double *dp;
    double *sp1;
    double *sp2;
    int i, elems;

    elems = r*c;

    /* malloc work arrays */
    if ((wx = (double *)malloc(elems*sizeof(double))) == NULL)
        return 30;    /* out of memory */

    if ((wy = (double *)malloc(elems*sizeof(double))) == NULL)
    {
```

```
        free(wx);
        return 30;      /* out of memory */
    }

    dp = wx;
    sp1 = x;

    /* square x into work area wx */
    for (i=0; i<elems; i++)
    {
        *dp = *sp1 * *sp1;
        ++sp1;
        ++dp;
    }

    dp = wy;
    sp2 = y;

    /* square y into work area wy */
    for (i=0; i<elems; i++)
    {
        *dp = *sp2 * *sp2;
        ++sp2;
        ++dp;
    }

    dp = h;
    sp1 = wx;
    sp2 = wy;

    /* compute hypotenuse into h which was allocated by GAUSS */
    for (i=0; i<elems; i++)
    {
        *dp = sqrt(*sp1 + *sp2);
        ++sp1;
        ++sp2;
        ++dp;
    }
```

```
    }

    /* free whatever you malloc */
    free(wx);
    free(wy);

    return 0;
}

/* exported wrapper, all double * arguments, calls the real
** function with whatever data types it expects
*/
int hypotenuse(double *x, double *y, double *h,
               double *r, double *c)
{
    return hypo( x, y, h, (int)*r, (int)*c );
}
```

The following Makefiles contain the compile and link commands you would use to build the dynamic library on various platforms. For explanations of the various flags used, see the documentation for your compiler and linker.

## Windows

```
hyp.dll: hyp.obj
link /dll /out:hyp.dll hyp.obj

hyp.obj: hyp.c
cl -c -MD -GX hyp.c
```

## Solaris

**\$(CCOPTS)** indicates any optional compilation flags you might add.

```
CCOPTIONS = -g -xsb -xarch=v9 -KPIC  
CC = cc
```

```
libhyp.so: hyp.c  
$(CC) -G $(CCOPTIONS) -o $@ hyp.c -lm
```

### Linux

**\$(CCOPTS)** indicates any optional compilation flags you might add.

```
CCOPTIONS = -g -O2 -lm -lc -shared  
CC = gcc
```

```
libhyp.so: hyp.cpp  
$(CC) $(CCOPTIONS) -o $@ hyp.c
```

For details on linking your dynamic library, see **dlibrary** in the GAUSS LANGUAGE REFERENCE.

# Data Transformations 21

**GAUSS** allows expressions that directly reference variables (columns) of a data set. This is done within the context of a data loop:

```
dataloop infile outfile;  
    drop wagefac wqlec shordelt foobly;  
    csed = ln(sqrt(csed));  
    select csed > 0.35 and married $== "y";  
    make chfac = hcfac + wcfac;  
    keep csed chfac stid recsum voom;  
enddata;
```

**GAUSS** translates the data loop into a procedure that performs the required operations, and then calls the procedure automatically at the location (in your program) of the data loop. It does this by translating your main program file into a temporary file and then executing the temporary file.

A data loop may be placed only in the main program file. Data loops in files that are **#include'd** or autoloaded are not recognized.

## 21.1 Data Loop Statements

A data loop begins with a **dataloop** statement and ends with an **enddata** statement. Inside a data loop, the following statements are supported:

<b>code</b>	Create variable based on a set of logical expressions.
<b>delete</b>	Delete rows (observations) based on a logical expression.
<b>drop</b>	Specify variables NOT to be written to data set.
<b>extern</b>	Allow access to matrices and strings in memory.
<b>keep</b>	Specify variables to be written to output data set.
<b>lag</b>	Lag variables a number of periods.
<b>listwise</b>	Control deletion of missing values.
<b>make</b>	Create new variable.
<b>outtyp</b>	Specify output file precision.
<b>recode</b>	Change variable based on a set of logical expressions.
<b>select</b>	Select rows (observations) based on a logical expression.
<b>vector</b>	Create new variable from a scalar returning expression.

In any expression inside a data loop, all text symbols not immediately followed by a left parenthesis ‘(’ are assumed to be data set variable (column) names. Text symbols followed by a left parenthesis are assumed to be procedure names. Any symbol listed in an **extern** statement is assumed to be a matrix or string already in memory.

## 21.2 Using Other Statements

All program statements in the main file and not inside a data loop are passed through to the temporary file without modification. Program statements within a data loop that are preceded by a '#' are passed through to the temporary file without modification. The user familiar with the code generated in the temporary file can use this to do out-of-the-ordinary operations inside the data loop.

## 21.3 Debugging Data Loops

The translator that processes data loops can be turned on and off. When the translator is on, there are three distinct phases in running a program:

<b>Translation</b>	Translation of main program file to temporary file.
<b>Compilation</b>	Compilation of temporary file.
<b>Execution</b>	Execution of compiled code.

### 21.3.1 Translation Phase

In the translation phase, the main program file is translated into a temporary file. Each data loop is translated into a procedure and a call to this procedure is placed in the temporary file at the same location as the original data loop. The data loop itself is commented out in the temporary file. All the data loop procedures are placed at the end of the temporary file.

Depending upon the status of line number tracking, error messages encountered in this phase will be printed with the file name and line numbers corresponding to the main file.

### 21.3.2 Compilation Phase

In the compilation phase, the temporary file is compiled. Depending upon the status of line number tracking, error messages encountered in this phase will be printed with the file name and

line numbers corresponding to both the main file and the temporary file.

### 21.3.3 Execution Phase

In the execution phase, the compiled program is executed. Depending on the status of line number tracking, error messages will include line number references from both the main file and the temporary file.

## 21.4 Reserved Variables

The following local variables are created by the translator and used in the produced code:

<code>x_cv</code>	<code>x_iptr</code>	<code>x_ncol</code>	<code>x_plag</code>
<code>x_drop</code>	<code>x_keep</code>	<code>x_nlag</code>	<code>x_ptrim</code>
<code>x_fpin</code>	<code>x_lval</code>	<code>x_nrow</code>	<code>x_shft</code>
<code>x_fpout</code>	<code>x_lvar</code>	<code>x_ntrim</code>	<code>x_tname</code>
<code>x_i</code>	<code>x_n</code>	<code>x_out</code>	<code>x_vname</code>
<code>x_in</code>	<code>x_name</code>	<code>x_outtyp</code>	<code>x_x</code>

These variables are reserved, and should not be used within a **dataloop... endata** section.



# Publication Quality Graphics 22

**GAUSS Publication Quality Graphics (PQG)** is a set of routines built on the graphics functions in **GraphiC** by Scientific Endeavors Corporation.

The main graphics routines include xy, xyz, surface, polar and log plots, as well as histograms, bar, and box graphs. Users can enhance their graphs by adding legends, changing fonts, and adding extra lines, arrows, symbols and messages.

The user can create a single full size graph, inset a smaller graph into a larger one, tile a window with several equally sized graphs or place several overlapping graphs in the window. Graphic panel size and location are all completely under the user's control.

## 22.1 General Design

**GAUSS PQG** consists of a set of main graphing procedures and several additional procedures and global variables for customizing the output.

All of the actual output to the window happens during the call to these main routines:

<b>bar</b>	Bar graphs.
<b>box</b>	Box plots.
<b>contour</b>	Contour plots.
<b>draw</b>	Draw graphs using only global variables.
<b>hist</b>	Histogram.
<b>histp</b>	Percentage histogram.
<b>histf</b>	Histogram from a vector of frequencies.
<b>loglog</b>	Log scaling on both axes.
<b>logx</b>	Log scaling on X axis.
<b>logy</b>	Log scaling on Y axis.
<b>polar</b>	Polar plots.
<b>surface</b>	3-D surface with hidden line removal.
<b>xy</b>	Cartesian graph.
<b>xyz</b>	3-D Cartesian graph.

## 22.2 Using Publication Quality Graphics

### 22.2.1 Getting Started

There are four basic parts to a graphics program. These elements should be in any program that uses graphics routines. The four parts are the header, data setup, graphics format setup, and graphics call.

## Header

In order to use the graphics procedures, the **pgraph** library must be activated. This is done in the **library** statement at the top of your program or command file. The next line in your program will typically be a command to reset the graphics global variables to their default state. For example:

```
library mylib, pgraph;  
graphset;
```

## Data Setup

The data to be graphed must be in matrices. For example:

```
x = seqa(1,1,50);  
y = sin(x);
```

## Graphics Format Setup

Most of the graphics elements contain defaults that allow the user to generate a plot without modification. These defaults, however, may be overridden by the user through the use of global variables and graphics procedures. Some of the elements that may be configured by the user are axes numbering, labeling, cropping, scaling, line and symbol sizes and types, legends, and colors.

## Calling Graphics Routines

The graphics routines take as input the user data and global variables that have previously been set. It is in these routines where the graphics file is created and displayed.

Following are three PQG examples. The first two programs are different versions of the same graph. The variables that begin with **\_p** are the global control variables used by the graphics

routines. (For a detailed description of these variables, see GLOBAL CONTROL VARIABLES, Section 22.6.

**Example 1** The routine being called here is a simple XY plot. The entire window will be used. Four sets of data will be plotted with the line and symbol attributes automatically selected. This graph will include a legend, title, and a time/date stamp (time stamp is on by default):

```
library pgraph;          /* activate PGRAPH library */
graphset;                /* reset global variables */
x = seqa(.1,.1,100);     /* generate data */
y = sin(x);
y = y ~ y*.8 ~ y*.6 ~ y*.4; /* 4 curves plotted against x */
_plegctl = 1;           /* legend on */
title("Example xy Graph"); /* Main title */
xy(x,y);                 /* Call to main routine */
```

**Example 2** Here is the same graph with more of the graphics format controlled by the user. The first two data sets will be plotted using symbols at data points only (observed data); the data points in the second two sets will be connected with lines (predicted results):

```
library pgraph;          /* activate PGRAPH library */
graphset;                /* reset global variables */
x = seqa(.1,.1,100);     /* generate data */
y = sin(x);
y = y ~ y*.8 ~ y*.6 ~ y*.4; /* 4 curves plotted against x */
_pdate = "";            /* date is not printed */
_plctrl = { 1, 1, 0, 0 }; /* 2 curves w/symbols, 2 without */
_pltype = { 1, 2, 6, 6 }; /* dashed, dotted, solid lines */
_pstype = { 1, 2, 0, 0 }; /* symbol types circles, squares */
_plegctl= { 2, 3, 1.7, 4.5 }; /* legend size and locations */
_plegstr= "Sin wave 1.\0"\ /* 4 lines legend text */
          "Sin wave .8\0"\
          "Sin wave .6\0"\
          "Sin wave .4";
ylabel("Amplitude");     /* Y axis label */
```

```
xlabel("X Axis");           /* X axis label */
title("Example xy Graph");   /* main title */
xy(x,y);                     /* call to main routine */
```

**Example 3** In this example, two graphics panels are drawn. The first is a full-sized surface representation, and the second is a half-sized inset containing a contour of the same data located in the lower left corner of the window:

```
library pgraph;              /* activate pgraph library */

/* Generate data for surface and contour plots */
x = seqa(-10,0.1,71)';      /* note x is a row vector */
y = seqa(-10,0.1,71);       /* note y is a column vector */
z = cos(5*sin(x) - y);       /* z is a 71x71 matrix */

begwind;                     /* initialize graphics windows */
makewind(9,6.855,0,0,0);     /* first window full size */
makewind(9/2,6.855/2,1,1,0); /* second window inset to first */

setwind(1);                  /* activate first window */
graphset;                    /* reset global variables */
_pzclr = { 1, 2, 3, 4 };     /* set Z level colors */
title("cos(5*sin(x) - y)");   /* set main title */
xlabel("X Axis");             /* set X axis label */
ylabel("Y Axis");             /* set Y axis label */
scale3d(miss(0,0),miss(0,0),-5|5); /* scale Z axis */
surface(x,y,z);               /* call surface routine */

nextwind;                    /* activate second window */
graphset;                    /* reset global variables */
_pzclr = { 1, 2, 3, 4 };     /* set Z level colors */
_pbox = 15;                  /* white border */
contour(x,y,z);               /* call contour routine */

endwind;                      /* Display windows */
```

While the structure has changed somewhat, the four basic elements of the graphics program are all here. The additional routines **begwind**, **endwind**, **makewind**, **nextwind**, and **setwind** are all used to control the graphic panels.

As Example 3 illustrates, the code between graphic panel functions (that is, **setwind** or **nextwind**) may include assignments to global variables, a call to **graphset**, or may set up new data to be passed to the main graphics routines.

You are encouraged to run the example programs supplied with **GAUSS**. Analyzing these programs is perhaps the best way to learn how to use the PQG system. The example programs are located on the `examples` subdirectory.

### 22.2.2 Graphics Coordinate System

PQG uses a 4190×3120 pixel resolution grid on a 9.0×6.855-inch printable area. There are three units of measure supported with most of the graphics global elements:

#### Inch Coordinates

Inch coordinates are based on the dimensions of the full-size 9.0×6.855-inch output page. The origin is (0,0) at the lower left corner of the page. If the picture is rotated, the origin is at the upper left. (For more information, see `INCH UNITS IN GRAPHIC PANELS`, Section [22.3.5](#).)

#### Plot Coordinates

Plot coordinates refer to the coordinate system of the graph in the units of the user's X, Y and Z axes.

#### Pixel Coordinates

Pixel coordinates refer to the 4096×3120 pixel coordinates of the full-size output page. The origin is (0,0) at the lower left corner of the page. If the picture is rotated, the origin is at the upper left.

## 22.3 Graphic Panels

Multiple graphic panels for graphics are supported. These graphic panels allow the user to display multiple graphs on one window or page.

A graphic panel is any rectangular subsection of the window or page. Graphic panels may be any size and position on the window and may be tiled or overlapping, transparent or nontransparent.

### 22.3.1 Tiled Graphic Panels

Tiled graphic panels do not overlap. The window can easily be divided into any number of tiled graphic panels with the **window** command. **window** takes three parameters: number of rows, number of columns, and graphic panel attribute (1=transparent, 0=nontransparent).

This example will divide the window into six equally sized graphic panels. There will be two rows of three graphic panels—three graphic panels in the upper half of the window and three in the lower half. The attribute value of 0 is arbitrary since there are no other graphic panels beneath them.

```
window(nrows,ncols,attr);  
window(2,3,0);
```

### 22.3.2 Overlapping Graphic Panels

Overlapping graphic panels are laid on top of one another as they are created, much as if you were using the cut and paste method to place several graphs together on one page. An overlapping graphic panel is created with the **makewind** command.

In this example, **makewind** will create an overlapping graphic panel that is 4 inches wide by 2.5 inches tall, positioned 1 inch from the left edge of the page and 1.5 inches from the bottom of the page. It will be nontransparent:

```
makewind(hsize,vsize,hpos,vpos,attr);
```

```
window(2,3,0);  
makewind(4,2.5,1,1.5,0);
```

### 22.3.3 Nontransparent Graphic Panels

A nontransparent graphic panel is one that is blanked before graphics information is written to it. Therefore, information in any previously drawn graphic panels that lie under it will not be visible.

### 22.3.4 Transparent Graphic Panels

A transparent graphic panel is one that is not blanked, allowing the graphic panel beneath it to “show through”. Lines, symbols, arrows, error bars, and other graphics objects may extend from one graphic panel to the next by using transparent graphic panels. First, create the desired graphic panel configuration. Then create a full-window, transparent graphic panel using the **makewind** or **window** command. Set the appropriate global variables to position the desired object on the transparent graphic panel. Use the **draw** procedure to draw it. This graphic panel will act as a transparent “overlay” on top of the other graphic panels. Transparent graphic panels can be used to add text or to superimpose one graphic panel on top of another.

### 22.3.5 Using Graphic Panel Functions

The following is a summary of the graphic panel functions:

<b>begwind</b>	Graphic panel initialization procedure.
<b>endwind</b>	End graphic panel manipulations, display graphs.
<b>window</b>	Partition window into tiled graphic panels.
<b>makewind</b>	Create graphic panel with specified size and position.
<b>setwind</b>	Set to specified graphic panel number.



---

<b>nextwind</b>	Set to next available graphic panel number.
<b>getwind</b>	Get current graphic panel number.
<b>savewind</b>	Save graphic panel configuration to a file.
<b>loadwind</b>	Load graphic panel configuration from a file.

This example creates four tiled graphic panels and one graphic panel that overlaps the other four:

```

library pgraph;
graphset;
begwind;

window(2,2,0); /* Create four tiled graphic panels
                (2 rows, 2 columns) */

xsize = 9/2;    /* Create graphic panel that overlaps the
                tiled graphic panels */
ysize = 6.855/2;
makewind(xsize,ysize,xsize/2,ysize/2,0);

x = seqa(1,1,1000); /* Create X data */
y = (sin(x) + 1) * 10.; /* Create Y data */

setwind(1);      /* Graph #1, upper left corner */
xy(x,y);
nextwind;        /* Graph #2, upper right corner */
logx(x,y);
nextwind;        /* Graph #3, lower left corner */
logy(x,y);
nextwind;        /* Graph #4, lower right corner */
loglog(x,y);
nextwind;        /* Graph #5, center, overlaid */
bar(x,y);
endwind;         /* End graphic panel processing,
                display graph */

```

### 22.3.6 Inch Units in Graphic Panels

Some global variables allow coordinates to be input in inches. If a coordinate value is in inches and is being used in a graphic panel, that value will be scaled to “graphic panel inches” and positioned relative to the lower left corner of the graphic panel. A “graphic panel inch” is a true inch in size only if the graphic panel is scaled to the full window, otherwise X coordinates will be scaled relative to the horizontal graphic panel size and Y coordinates will be scaled relative to the vertical graphic panel size.

### 22.3.7 Saving Graphic Panel Configurations

The functions **savewind** and **loadwind** allow the user to save graphic panel configurations. Once graphic panels are created (using **makewind** and **window**), **savewind** may be called. This will save to disk the global variables containing information about the current graphic panel configuration. To load this configuration again, call **loadwind**. (See **loadwind** in the GAUSS LANGUAGE REFERENCE.

## 22.4 Graphics Text Elements

Graphics text elements, such as titles, messages, axes labels, axes numbering, and legends, can be modified and enhanced by changing fonts and by adding superscripting, subscripting, and special mathematical symbols.

To make these modifications and enhancements, the user can embed “escape codes” in the text strings that are passed to **title**, **xlabel**, **ylabel** and **asclabel** or assigned to **\_pmsgstr** and **\_plegstr**.

The escape codes used for graphics text are:

<code>\000</code>	String termination character (null byte).
<code>[</code>	Enter superscript mode, leave subscript mode.
<code>]</code>	Enter subscript mode, leave superscript mode.
<code>@</code>	Interpret next character as literal.
<code>\20n</code>	Select font number <i>n</i> . (see SELECTING FONTS, following).

The escape code `\L` (or `\l`) can be embedded into title strings to create a multiple line title:

```
title("This is the first line\lthis is the second line");
```

A null byte `\000` is used to separate strings in `_plegstr` and `_pmsgstr`:

```
_pmsgstr = "First string\000Second string\000Third string";
```

or

```
_plegstr = "Curve 1\000Curve 2";
```

Use `[. .]` to create the expression  $M(t) = E(e^{tx})$ :

```
_pmsgstr = "M(t) = E(e[tx])";
```

Use `@` to generate `[` and `]` in an X axis label:

```
xlabel("Data used for x is: data@[. ,1 2 3@]");
```

## 22.4.1 Selecting Fonts

Four fonts are supplied with the **Publication Quality Graphics** system. They are Simplex, Complex, Simgrma, and Microb. (For a list of the characters available in each font, see Appendix [A](#).)

Fonts are loaded by passing to the **fonts** procedure a string containing the names of all fonts to be loaded. For example, this statement will load all four fonts:

```
fonts("simplex complex microb simgrma");
```

The **fonts** command must be called before any of the fonts can be used in text strings. A font can then be selected by embedding an escape code of the form “\20*n*” in the string that is to be written in the new font. The *n* will be 1, 2, 3 or 4, depending on the order in which the fonts were loaded in **fonts**. If the fonts were loaded as in the previous example, the escape characters for each would be:

```
\201 Simplex  
\202 Complex  
\203 Microb  
\204 Simgrma
```

The following example demonstrates how to select a font for use in a string:

```
title("\201This is the title using Simplex font");  
xlabel("\202This is the label for X using Complex font");  
ylabel("\203This is the label for Y using Microb font");
```

Once a font is selected, all succeeding text will use that font until another font is selected. If no fonts are selected by the user, a default font (Simplex) is loaded and selected automatically for all text work.

### 22.4.2 Greek and Mathematical Symbols

The following examples illustrate the use of the Simgrma font; they assume that Simgrma was the fourth font loaded. (For the available Simgrma characters and their numbers, see [Appendix A](#).) The Simgrma characters are specified by either:

1. The character number, preceeded by a “\”.
2. The regular text character with the same number.

For example, to get an integral sign “ $\int$ ” in Simgrma, embed either a “`\044`” or a “`,`” in a string that has been set to use the Simgrma font.

To produce the title  $f(x) = \sin^2(\pi x)$ , the following title string should be used:

```
title("\201f(x) = sin[2](\204p\201x)");
```

The “**p**” (character 112) corresponds to “ $\pi$ ” in Simgrma.

To number the major X axis tick marks with multiples of  $\pi/4$ , the following could be passed to **asclabel**:

```
lab = "\2010 \204p\201/4 \204p\201/2 3\204p\201/4 \204p";
asclabel(lab,0);
xtics(0,pi,pi/4,1);
```

**xtics** is used to make sure that major tick marks are placed in the appropriate places.

This example will number the X axis tick marks with the labels  $\mu^{-2}$ ,  $\mu^{-1}$ , 1,  $\mu$ , and  $\mu^2$ :

```
lab = "\204m\201[-2] \204m\201[-1] 1 \204m m\201[2]";
asclabel(lab,0);
```

This example illustrates the use of several of the special Simgrma symbols:

```
_pmsgstr = "\2041\2011/2\204p ,\201e[-\204m[\2012]\201/2]d\204m";
```

This produces:

$$\sqrt{1/2\pi} \int e^{-\mu^2/2} d\mu$$

## 22.5 Colors

0	Black	8	Dark Grey
1	Blue	9	Light Blue
2	Green	10	Light Green
3	Cyan	11	Light Cyan
4	Red	12	Light Red
5	Magenta	13	Light Magenta
6	Brown	14	Yellow
7	Grey	15	White

## 22.6 Global Control Variables

The following global variables are used to control various graphics elements. Default values are provided. Any or all of these variables can be set before calling one of the main graphing routines. The default values can be modified by changing the declarations in `pgraph.dec` and the statements in the procedure **graphset** in `pgraph.src`. **graphset** can be called whenever the user wants to reset these variables to their default values.

**\_pageshf**      2×1 vector, the graph will be shifted to the right and up if this is not 0. If this is 0, the graph will be centered on the output page. Default is 0.

Note: Used internally. (For the same functionality, see **makewind** in the GAUSS LANGUAGE REFERENCE.) This is used by the graphic panel routines. The user must not set this when using the graphic panel procedures.

**\_pagesiz**      2×1 vector, size of the graph in inches on the printer output. Maximum size is 9.0×6.855 inches (unrotated) or 6.855×9.0 inches (rotated). If this is 0, the maximum size will be used. Default is 0.

Note: Used internally. (For the same functionality, see **makewind** in the GAUSS LANGUAGE REFERENCE). This is used by the graphic panel routines. The user must not set this when using the graphic panel procedures.

**\_parrow**      M×11 matrix, draws one arrow per row of the input matrix (for total of M arrows). If scalar zero, no arrows will be drawn.

[M,1] x starting point.

[M,2] y starting point.

[M,3] x ending point.

[M,4] y ending point.

[M,5] ratio of the length of the arrow head to half its width.

[M,6] size of arrow head in inches.

[M,7] type and location of arrow heads. This integer number will be interpreted as a decimal expansion  $mn$ , for example: if 10, then  $m = 1$ ,  $n = 0$ .

$m$ , type of arrow head:

0 solid

1 empty

2 open

3 closed

$n$ , location of arrow head:

0 none

1 at the final end

2 at both ends

[M,8] color of arrow, see COLORS, Section 22.5.

[M,9] coordinate units for location:

1 x,y starting and ending locations in plot coordinates

2 x,y starting and ending locations in inches

3 x,y starting and ending locations in pixels

[M,10] line type:

1 dashed

2 dotted

3 short dashes

4 closely spaced dots

5 dots and dashes

6 solid

[M,11] controls thickness of lines used to draw arrow. This value may be zero or greater. A value of zero is normal line width.

To create two single-headed arrows, located using inches, use

```
_parrow = { 1 1 2 2 3 0.2 11 10 2 6 0,
            3 4 2 2 3 0.2 11 10 2 6 0 };
```

**\_parrow3** M×12 matrix, draws one 3-D arrow per row of the input matrix (for a total of M arrows). If scalar zero, no arrows will be drawn.

[M,1] x starting point in 3-D plot coordinates.

[M,2] y starting point in 3-D plot coordinates.

[M,3] z starting point in 3-D plot coordinates.

[M,4] x ending point in 3-D plot coordinates.

[M,5] y ending point in 3-D plot coordinates.

[M,6] z ending point in 3-D plot coordinates.

[M,7] ratio of the length of the arrow head to half its width.

[M,8] size of arrow head in inches.

[M,9] type and location of arrow heads. This integer number will be interpreted as a decimal expansion  $mn$ . For example: if 10, then  $m = 1$ ,  $n = 0$ .

$m$ , type of arrow head:

- 0** solid
- 1** empty
- 2** open
- 3** closed

$n$ , location of arrow head:

- 0** none
- 1** at the final end
- 2** at both ends

[M,10] color of arrow, see **COLORS**, Section [22.5](#).



[M,11] line type:

- 1 dashed
- 2 dotted
- 3 short dashes
- 4 closely spaced dots
- 5 dots and dashes
- 6 solid

[M,12] controls thickness of lines used to draw arrow. This value may be zero or greater. A value of zero is normal line width.

To create two single-headed arrows, located using plot coordinates, use

```
_parrow3 = { 1 1 1 2 2 2 3 0.2 11 10 6 0,
              3 4 5 2 2 2 3 0.2 11 10 6 0 };
```

**\_paxes**

scalar, 2×1, or 3×1 vector for independent control for each axis. The first element controls the X axis, the second controls the Y axis, and the third (if set) controls the Z axis. If 0 the axis will not be drawn. Default is 1.

If this is a scalar, it will be expanded to that value.

For example:

```
_paxes = { 1, 0 }; /* turn X axis on, Y axis off */
_paxes = 0;        /* turn all axes off */
_paxes = 1;        /* turn all axes on */
```

**\_paxht**

scalar, size of axes labels in inches. If 0, a default size will be computed. Default is 0.

**\_pbartyp**

1×2 or K×2 matrix. Controls bar shading and colors in bar graphs and histograms.

The first column controls the bar shading:

- 0 no shading
- 1 dots

- 2 vertical cross-hatch
- 3 diagonal lines with positive slope
- 4 diagonal lines with negative slope
- 5 diagonal cross-hatch
- 6 solid

The second column controls the bar color, see **COLORS**, Section 22.5.

- \_pbarwid** scalar, width of bars in bar graphs and histograms. The valid range is 0-1. If 0, the bars will be a single pixel wide. If 1, the bars will touch each other. Default is 0.5, so the bars take up about half the space open to them.
- \_pbox** scalar, draws a box (border) around the entire graph. Set to desired color of box to be drawn. Use 0 if no box is desired. Default is 0.
- \_pboxctl** 5×1 vector, controls box plot style, width, and color. Used by procedure **box** only.
- [1] box width between 0 and 1. If 0, the box plot is drawn as two vertical lines representing the quartile ranges with a filled circle representing the 50<sup>th</sup> percentile.
  - [2] box color, see **COLORS**, Section 22.5. If 0, the colors may be individually controlled using global variable **\_pcolor**.
  - [3] min/max style for the box symbol. One of the following:
    - 1 minimum and maximum taken from the actual limits of the data. Elements 4 and 5 are ignored.
    - 2 statistical standard with the minimum and maximum calculated according to interquartile range as follows:
$$\begin{aligned} \text{intqrang} &= 75^{\text{th}} - 25^{\text{th}} \\ \text{min} &= 25^{\text{th}} - 1.5 \text{ intqrang} \\ \text{max} &= 75^{\text{th}} + 1.5 \text{ intqrang} \end{aligned}$$
Elements 4 and 5 are ignored.
    - 3 minimum and maximum percentiles taken from elements 4 and 5.
  - [4] minimum percentile value (0-100) if **\_pboxctl**[3] = 3.
  - [5] maximum percentile value (0-100) if **\_pboxctl**[3] = 3.

**\_pboxlim** 5×M output matrix containing computed percentile results from procedure **box**. M corresponds to each column of input y data.

[1,M] minimum whisker limit according to **\_pboxctl**[3].

[2,M] 25th percentile (bottom of box).

[3,M] 50th percentile (median).

[4,M] 75th percentile (top of box).

[5,M] maximum whisker limit according to **\_pboxctl**[3].

**\_pcolor** scalar or K×1 vector, colors for main curves in **xy**, **xyz** and **log** graphs. To use a single color set for all curves set this to a scalar color value. If 0, use default colors. Default is 0.

The default colors come from a global vector called **\_pcsel**. This vector can be changed by editing **pgraph.dec** to change the default colors, see **COLORS**, Section 22.5 (**\_pcsel** is not documented elsewhere).

**\_pcrop** scalar or 1×5 vector, allows plot cropping for different graphic elements to be individually controlled. Valid values are 0 (disabled) or 1 (enabled). If cropping is enabled, any graphical data sent outside the axes area will not be drawn. If this is a scalar, it is expanded to a 1×5 vector using the given value for all elements. All cropping is enabled by default.

[1] crop main curves/symbols.

[2] crop lines generated using **\_pline**.

[3] crop arrows generated using **\_parrow**.

[4] crop circles/arcs generated using **\_pline**.

[5] crop symbols generated using **\_psym**.

This example will crop main curves, and lines and circles drawn by **\_pline**.

```
_pcrop = { 1 1 0 1 0 };
```

**\_pcross** scalar. If 1, the axes will intersect at the (0,0) X-Y location if it is visible. Default is 0, meaning the axes will be at the lowest end of the X-Y coordinates.

**\_pdate** date string. If this contains characters, the date will be appended and printed. The default is set as follows (the first character is a font selection escape code):

```
_pdate = "\201GAUSS  ";
```

If this is set to a null string, no date will be printed. (For more information on using fonts within strings, see [GRAPHICS TEXT ELEMENTS, Section 22.4](#).

**\_perrbar** M×9 matrix, draws one error bar per row of the input matrix. If scalar 0, no error bars will be drawn. Location values are in plot coordinates.

[M,1] x location.

[M,2] left end of error bar.

[M,3] right end of error bar.

[M,4] y location.

[M,5] bottom of error bar.

[M,6] top of error bar.

[M,7] line type:

- 1 dashed
- 2 dotted
- 3 short dashes
- 4 closely spaced dots
- 5 dots and dashes
- 6 solid

[M,8] color, see [COLORS, Section 22.5](#).

[M,9] line thickness.. This value may be 0 or greater. A value of 0 is normal line width.

To create one error bar using solid lines, use

```
_perrbar = { 1 0 2 2 1 3 6 2 0 };
```

**\_pframe** 2×1 vector, controls frame around axes area. On 3-D plots this is a cube surrounding the 3-D workspace.

- [1] 1 frame on  
0 frame off
- [2] 1 tick marks on frame  
0 no tick marks

The default is a frame with tick marks.

### **\_pgrid**

2×1 vector to control grid.

- [1] grid through tick marks:
  - 0 no grid
  - 1 dotted grid
  - 2 fine dotted grid
  - 3 solid grid
- [2] grid subdivisions between major tick marks:
  - 0 no subdivisions
  - 1 dotted lines at subdivisions
  - 2 tick marks only at subdivisions

The default is no grid and tick marks at subdivisions.

### **\_plctrl**

scalar or K×1 vector to control whether lines and/or symbols will be displayed for the main curves. This also controls the frequency of symbols on main curves. The number of rows (K) is equal to the number of individual curves to be plotted in the graph. Default is 0.

- 0 draw line only.
- >0 draw line and symbols every **\_plctrl** points.
- <0 draw symbols only every **\_plctrl** points.
- 1 all of the data points will be plotted with no connecting lines.

This example draws a line for the first curve, draws a line and plots a symbol every 10 data points for the second curve, and plots symbols only every 5 data points for the third curve:

```
_plctrl = { 0, 10, -5 };
```

**\_plegctl** scalar or 1×4 vector, legend control variable.  
If scalar 0, no legend is drawn (default). If nonzero scalar, create legend in the default location in the lower right of the page.

If 1×4 vector, set as follows:

- [1] legend position coordinate units:
  - 1 coordinates are in plot coordinates
  - 2 coordinates are in inches
  - 3 coordinates are in pixel
- [2] legend text font size, where  $1 \leq \text{size} \leq 9$ . Default is 5.
- [3] x coordinate of lower left corner of legend box.
- [4] y coordinate of lower left corner of legend box.

This example puts a legend in the lower right corner:

```
_plegctl = 1;
```

This example creates a smaller legend and positions it 2.5 inches from the left and 1 inch from the bottom.

```
_plegctl = { 2 3 2.5 1 };
```

**\_plegstr** string, legend entry text. Text for multiple curves is separated by a null byte (“\000”).

For example:

```
_plegstr = "Curve 1\000Curve 2\000Curve 3";
```

**\_plev** M×1 vector, user-defined contour levels for **contour**. Default is 0. (See **contour** in the GAUSS LANGUAGE REFERENCE.)

**\_pline** M×9 matrix, to draw lines, circles, or radii. Each row controls one item to be drawn. If this is a scalar zero, nothing will be drawn. Default is 0.

[M,1] item type and coordinate system:

- 1 line in plot coordinates
- 2 line in inch coordinates
- 3 line in pixel coordinates
- 4 circle in plot coordinates
- 5 circle in inch coordinates
- 6 radius in plot coordinates
- 7 radius in inch coordinates

[M,2] line type:

- 1 dashed
- 2 dotted
- 3 short dashes
- 4 closely spaced dots
- 5 dots and dashes
- 6 solid

[M,3-7] coordinates and dimensions:

if item type is line ( $1 \leq \text{\_pline}[M,1] \leq 3$ ):

[M,3] x starting point.

[M,4] y starting point.

[M,5] x ending point.

[M,6] y ending point.

[M,7] 0 if this is a continuation of a curve, 1 if this begins a new curve.

if item type is circle ( $\text{\_pline}[M,1] = 4$  or  $\text{\_pline}[M,1] = 5$ ):

[M,3] x center of circle.

[M,4] y center of circle.

[M,5] radius.

[M,6] starting point of arc in radians.

[M,7] ending point of arc in radians.

if item type is radius ( $\text{\_pline}[M,1] = 6$  or  $\text{\_pline}[M,1] = 7$ ):

[M,3] x center of circle.

[M,4] y center of circle.

[M,5] beginning point of radius, 0 is the center of the circle.

[M,6] ending point of radius.

[M,7] angle in radians.

[M,8] color, see **COLORS**, Section 22.5.

[M,9] controls line thickness. This value may be zero or greater. A value of zero is normal line width.

**\_pline3d** M×9 matrix. Allows extra lines to be added to an **xyz** or **surface** graph in 3-D plot coordinates.

[M,1] x starting point.

[M,2] y starting point.

[M,3] z starting point.

[M,4] x ending point.

[M,5] y ending point.

[M,6] z ending point.

[M,7] color.

[M,8] line type:

- 1 dashed
- 2 dotted
- 3 short dashes
- 4 closely spaced dots
- 5 dots and dashes
- 6 solid

[M,9] line thickness, 0 = normal width.

[M,10] hidden line flag, 1 = obscured by surface, 0 = not obscured.

**\_plotshf** 2×1 vector, distance of plot from lower left corner of output page in inches.

[1] x distance.

[2] y distance.

If scalar 0, there will be no shift. Default is 0.

Note: Used internally. (For the same functionality, see **axmargin** in the GAUSS LANGUAGE REFERENCE.) This is used by the graphic panel routines. The user must not set this when using the graphic panel procedures.



<b><code>_plotsiz</code></b>	<p>2×1 vector, size of the axes area in inches. If scalar 0, the maximum size will be used.</p> <p>Note: Used internally. (For the same functionality, see <b><code>axmargin</code></b> in the GAUSS LANGUAGE REFERENCE.) This is used by the graphic panel routines. The user must not set this when using the graphic panel procedures.</p>
<b><code>_pltype</code></b>	<p>scalar or K×1 vector, line type for the main curves. If this is a nonzero scalar, all lines will be this type. If scalar 0, line types will be default styles. Default is 0.</p> <ol style="list-style-type: none"> <li>1    dashed</li> <li>2    dotted</li> <li>3    short dashes</li> <li>4    closely spaced dots</li> <li>5    dots and dashes</li> <li>6    solid</li> </ol> <p>The default line types come from a global vector called <b><code>_plsel</code></b>. This vector can be changed by editing <code>pgraph.dec</code> to change the default line types (<b><code>_plsel</code></b> is not documented elsewhere.)</p>
<b><code>_plwidth</code></b>	<p>scalar or K×1 vector, line thickness for main curves. This value may be zero or greater. A value of zero is normal (single pixel) line width. Default is 0.</p>
<b><code>_pmcolor</code></b>	<p>9×1 vector, color values to use for plot, see COLORS, Section 22.5.</p> <ol style="list-style-type: none"> <li>[1]   axes.</li> <li>[2]   axes numbers.</li> <li>[3]   X axis label.</li> <li>[4]   Y axis label.</li> <li>[5]   Z axis label.</li> <li>[6]   title.</li> <li>[7]   box.</li> <li>[8]   date.</li> <li>[9]   background.</li> </ol>

If this is scalar, it will be expanded to a 9×1 vector.

**\_pmsgctl** L×7 matrix of control information for printing the strings contained in **\_pmsgstr**.

[L,1] horizontal location of lower left corner of string.

[L,2] vertical location of lower left corner of string.

[L,3] character height in inches.

[L,4] angle in degrees to print string. This may be -180 to 180 relative to the positive X axis.

[L,5] location coordinate system.

1 location of string in plot coordinates

2 location of string in inches

[L,6] color.

[L,7] font thickness, may be 0 or greater. If 0 use normal line width.

**\_pmsgstr** string, contains a set of messages to be printed on the plot. Each message is separated from the next by a null byte (\000). The number of messages must correspond to the number of rows in the **\_pmsgctl** control matrix. This can be created as follows:

```
_pmsgstr = "Message one.\000Message two.";
```

**\_pnotify** scalar, controls window output during the creation of the graph. Default is 1.

0 no activity to the window while writing .tkf file

1 display progress as fonts are loaded, and .tkf file is being generated

**\_pnum** scalar, 2×1 or 3×1 vector for independent control for axes numbering. The first element controls the X axis numbers, the second controls the Y axis numbers, and the third (if set) controls the Z axis numbers. Default is 1.

If this value is scalar, it will be expanded to a vector.

0 no axes numbers displayed

1 axes numbers displayed, vertically oriented on axis

**2** axes numbers displayed, horizontally oriented on axis

For example:

```
_pnum = { 0, 2 }; /* no X axis numbers, */
                /* horizontal on Y axis */
```

<b>_pnumht</b>	scalar, size of axes numbers in inches. If 0, a size of .13 will be used. Default is 0.
<b>_prostate</b>	scalar. If 0, no rotation, if 1, plot will be rotated 90 degrees. Default is 0.
<b>_pscreen</b>	scalar. If 1, display graph in window, if 0, do not display graph in window. Default is 1.
<b>_psilent</b>	scalar. If 0, a beep will sound when the graph is finished drawing to the window. Default is 1 (no beep).
<b>_pstype</b>	scalar or K×1 vector, controls symbol used at data points. To use a single symbol type for all points, set this to one of the following scalar values:

<b>1</b>	circle	<b>8</b>	solid circle
<b>2</b>	square	<b>9</b>	solid square
<b>3</b>	triangle	<b>10</b>	solid triangle
<b>4</b>	plus	<b>11</b>	solid plus
<b>5</b>	diamond	<b>12</b>	solid diamond
<b>6</b>	inverted triangle	<b>13</b>	solid inverted triangle
<b>7</b>	star	<b>14</b>	solid star

If this is a vector, each line will have a different symbol. Symbols will repeat if there are more lines than symbol types. Default is 0 (no symbols are shown).

<b>_psurf</b>	2×1 vector, controls 3-D surface characteristics.
<b>[1]</b>	if 1, show hidden lines. Default is 0.
<b>[2]</b>	color for base, see COLORS, Section 22.5. The base is an outline of the X-Y plane with a line connecting each corner to the surface. If 0, no base is drawn. Default is 7.

<b>_psym</b>	<p>M×7 matrix, M extra symbols will be plotted.</p> <p>[M,1] x location.</p> <p>[M,2] y location.</p> <p>[M,3] symbol type, see <b>_pstype</b> earlier.</p> <p>[M,4] symbol height. If this is 0, a default height of 5.0 will be used.</p> <p>[M,5] symbol color, see COLORS, Section <a href="#">22.5</a>.</p> <p>[M,6] type of coordinates:</p> <ul style="list-style-type: none"><li>1 plot coordinates</li><li>2 inch coordinates</li></ul> <p>[M,7] line thickness. A value of zero is normal line width.</p>
<b>_psym3d</b>	<p>M×7 matrix for plotting extra symbols on a 3-D (<b>surface</b> or <b>xyz</b>) graph.</p> <p>[M,1] x location in plot coordinates.</p> <p>[M,2] y location in plot coordinates.</p> <p>[M,3] z location in plot coordinates.</p> <p>[M,4] symbol type, see <b>_pstype</b> earlier.</p> <p>[M,5] symbol height. If this is 0, a default height of 5.0 will be used.</p> <p>[M,6] symbol color, see COLORS, Section <a href="#">22.5</a>.</p> <p>[M,7] line thickness. A value of 0 is normal line width.</p> <p>Use <b>_psym</b> for plotting extra symbols in inch coordinates.</p>
<b>_psymsiz</b>	<p>scalar or K×1 vector, symbol size for the symbols on the main curves. This is NOT related to <b>_psym</b>. If 0, a default size of 5.0 is used.</p>
<b>_ptek</b>	<p>string, name of Tektronix format graphics file. This must have a <b>.tkf</b> extension. If this is set to a null string, the graphics file will be suppressed. The default is <b>graphic.tkf</b>.</p>
<b>_pticout</b>	<p>scalar. If 1, tick marks point outward on graphs. Default is 0.</p>
<b>_ptitlht</b>	<p>scalar, the height of the title characters in inches. If this is 0, a default height of approx. 0.13 inch will be used.</p>

<b>_pversno</b>	string, the graphics version number.
<b>_pxpmax</b>	scalar, the maximum number of places to the right of the decimal point for the X axis numbers. Default is 12.
<b>_pxsci</b>	scalar, the threshold in digits above which the data for the X axis will be scaled and a power of 10 scaling factor displayed. Default is 4.
<b>_pypmax</b>	scalar, the maximum number of places to the right of the decimal point for the Y axis numbers. Default is 12.
<b>_pysci</b>	scalar, the threshold in digits above which the data for the Y axis will be scaled and a power of 10 scaling factor displayed. Default is 4.
<b>_pzclr</b>	scalar, row vector, or K×2 matrix, Z level color control for procedures <b>surface</b> and <b>contour</b> . (See <b>surface</b> in the GAUSS LANGUAGE REFERENCE.)
<b>_pzoom</b>	1×3 row vector, magnifies the graphics display for zooming in on detailed areas of the graph. If scalar 0, no magnification is performed. Default is 0.  <div> <div>[1] magnification value. 1 is normal size.</div> <div>[2] horizontal center of zoomed plot (0-100).</div> <div>[3] vertical center of zoomed plot (0-100).</div> </div> <p>To see the upper left quarter of the screen magnified 2 times use:</p> <pre>_pzoom = { 2 25 75 };</pre>
<b>_pzpmax</b>	scalar, the maximum number of places to the right of the decimal point for the Z axis numbers. Default is 3.
<b>_pzsci</b>	scalar, the threshold in digits above which the data for the Z axis will be scaled and a power of 10 scaling factor displayed. Default is 4.



# ATOG 23

ATOG is a stand-alone conversion utility that converts ASCII files into **GAUSS** data sets. ATOG can convert delimited and packed ASCII files into **GAUSS** data sets. ATOG can be run from a batch file or the command line.

The syntax is:

```
atog cmdfile
```

where *cmdfile* is the name of the command file. If no extension is given, `.cmd` will be assumed. If no command file is specified, a command summary will be displayed.

## 23.1 Command Summary

The following commands are supported in ATOG:

<b>append</b>	Append data to an existing file.
---------------	----------------------------------

<b>complex</b>	Treat data as complex variables.
<b>input</b>	The name of the ASCII input file.
<b>invar</b>	Input file variables (column names).
<b>msym</b>	Specify missing value character.
<b>nocheck</b>	Don't check data type or record length.
<b>output</b>	The name of the <b>GAUSS</b> data set to be created.
<b>outtyp</b>	Output data type.
<b>outvar</b>	List of variables to be included in output file.
<b>preserve</b>	Preserve case of variable names in output file.

The principle commands for converting an ASCII file that is delimited with spaces or commas are given in the following example:

```
input agex.asc;  
output agex;  
invar $ race # age pay $ sex region;  
outvar region age sex pay;  
outtyp d;
```

In this example, a delimited ASCII file `agex.asc` is converted to a double precision **GAUSS** data file `agex.dat`. The input file has five variables. The file will be interpreted as having five columns:

column	name	data type
1	race	character
2	AGE	numeric
3	PAY	numeric
4	sex	character
5	region	character



The output file will have four columns since the first column of the input file (race) is not included in the output variables. The columns of the output file are:

column	name	data type
1	region	character
2	AGE	numeric
3	sex	character
4	PAY	numeric

The variable names are saved in the file header. Unless **preserve** has been specified, the names of character variables will be saved in lowercase, and the names of numeric variables will be saved in uppercase. The **\$** in the **invar** statement specifies that the variables that follow are character type. The **#** specifies numeric. If **\$** and **#** are not used in an **invar** statement, the default is numeric.

Comments in command files must be enclosed between '@' characters.

## 23.2 Commands

A detailed explanation of each command follows.

### append

Instructs ATOG to append the converted data to an existing data set:

```
append;
```

No assumptions are made regarding the format of the existing file. Make certain that the number, order, and type of data converted match the existing file. ATOG creates v96 format data files, so will only append to v96 format data files.

### **complex**

Instructs ATOG to convert the ASCII file into a complex **GAUSS** data set:

```
complex;
```

Complex **GAUSS** data sets are stored by rows, with the real and imaginary parts interleaved, element by element. ATOG assumes the same structure for the ASCII input file, and will thus read TWO numbers out for EACH variable specified.

**complex** cannot be used with packed ASCII files.

### **input**

Specifies the file name of the ASCII file to be converted. The full path name can be used in the file specification.

For example, the command:

```
input data.raw;
```

will expect an ASCII data file in the current working directory.

The command:

```
input /research/data/myfile.asc;
```

specifies a file to be located in the `/research/data` subdirectory.

**invar**

**Soft Delimited ASCII Files** Soft delimited files may have spaces, commas, or cr/lf as delimiters between elements. Two or more consecutive delimiters with no data between them are treated as one delimiter. For example:

```
invar age $ name sex # pay var[1:10] x[005];
```

The **invar** command above specifies the following variables:

column	name	data type
1	AGE	numeric
2	name	character
3	sex	character
4	PAY	numeric
5	VAR01	numeric
6	VAR02	numeric
7	VAR03	numeric
8	VAR04	numeric
9	VAR05	numeric
10	VAR06	numeric
11	VAR07	numeric
12	VAR08	numeric
13	VAR09	numeric
14	VAR10	numeric
15	X001	numeric
16	X002	numeric
17	X003	numeric
18	X004	numeric
19	X005	numeric

As the input file is translated, the first 19 elements will be interpreted as the first row (observation), the next 19 will be interpreted as the second row, and so on. If the number of elements in the file is not evenly divisible by 19, the final incomplete row will be dropped and a warning message will be given.

**Hard Delimited ASCII Files** Hard delimited files have a printable character as a delimiter between elements. Two delimiters without intervening data between them will be interpreted as a missing. If `\n` is specified as a delimiter, the file should have one element per line and blank lines will be considered missings. Otherwise, delimiters must be printable characters. The dot `'.'` is illegal and will always be interpreted as a missing value. To specify the backslash as a delimiter, use `\\`. If `\r` is specified as a delimiter, the file will be assumed to contain one case or record per line with commas between elements and no comma at the end of the line.

For hard delimited files the **delimit** subcommand is used with the **invar** command. The **delimit** subcommand has two optional parameters. The first parameter is the delimiter. The default is a comma. The second parameter is an 'N'. If the second parameter is present, ATOG will expect N delimiters. If it is not present, ATOG will expect N-1 delimiters.

This example:

```
invar delimit(, N) $ name # var[5];
```

will expect a file like this:

```
BILL , 222.3, 123.2, 456.4, 345.2, 533.2,  
STEVE, 624.3, 340.3,      , 624.3, 639.5,  
TOM , 244.2, 834.3, 602.3, 333.4, 822.5,
```

while

```
invar delimit(,) $ name # var[5];
```

or

```
invar delimit $ name # var[5];
```

will expect a file like this:

```
BILL , 222.3, 123.2, 456.4, 345.2, 533.2,
STEVE, 624.3, 340.3, , 624.3, 639.5,
TOM , 244.2, 834.3, 602.3, 333.4, 822.5
```

The difference between specifying N or N-1 delimiters can be seen here:

```
456.4, 345.2, 533.2,
, 624.3, 639.5,
602.3, 333.4,
```

If the **invar** statement specified three variables and N-1 delimiters, this file would be interpreted as having three rows containing a missing in the [2,1] element and the [3,3] element like this:

```
456.4 345.2 533.2
. 624.3 639.5
602.3 333.4 .
```

If N delimiters had been specified, this file would be interpreted as having two rows, and a final incomplete row that is dropped:

```
456.4 345.2 533.2
. 624.3 639.5
```

The spaces were shown only for clarity and are not significant in delimited files so:

```
BILL,222.3,123.2,456.4,345.2,533.2,
STEVE,624.3,340.3,,624.3,639.5,
TOM,244.2,834.3,602.3,333.4,822.5
```

would work just as well.

Linefeeds are significant only if **\n** is specified as the delimiter, or when using **\r**. This example:

```
invar delimit(\r) $ name # var[5];
```

will expect a file with no comma after the final element in each row:

```
BILL , 222.3, 123.2, 456.4, 345.2, 533.2
STEVE, 624.3, 340.3, 245.3, 624.3, 639.5
TOM , 244.2, 834.3, 602.3, 333.4, 822.5
```

**Packed ASCII Files** Packed ASCII files must have fixed length records. The **record** subcommand is used to specify the record length, and variables are specified by giving their type, starting position, length, and the position of an implicit decimal point if necessary.

**outvar** is not used with packed ASCII files. Instead, **invar** is used to specify only those variables to be included in the output file.

For packed ASCII files the syntax of the **invar** command is as follows:

```
invar record = reclen (format) variables (format) variables;
```

where,

*reclen* the total record length in bytes, including the final carriage return/line feed if applicable. Records must be fixed length.

*format* (*start,length,prec*) where:

*start* starting position of the field in the record, 1 is the first position. The default is 1.

*length* the length of the field in bytes. The default is 8.

*prec* optional; a decimal point will be inserted automatically *prec* places in from the RIGHT edge of the field.

If several variables are listed after a format definition, each succeeding field will be assumed to start immediately after the preceding field. If an asterisk is used to specify the starting position, the current logical default will be assumed. An asterisk in the length position will select the current default for both *length* and *prec*. This is illegal: (3,8.\*).

The type change characters **\$** and **#** are used to toggle between character and numeric data type.

Any data in the record that is not defined in a format is ignored.

The examples below assume a 32-byte record with a carriage return/line feed occupying the last 2 bytes of each record. The data below can be interpreted in different ways using different **invar** statements:

ABCDEF GHIJ 12345678901234567890<CR><LF>					
position	1	10	20	30	31 32

This example:

```
invar record=32 $(1,3) group dept #(11,4.2) x[3] (*,5) y;
```

will result in:

variable	value	type
group	ABC	character
dept	DEF	character
X1	12.34	numeric
X2	56.78	numeric
X3	90.12	numeric
Y	34567	numeric

This example:

```
invar record=32 $ dept (*,2) id # (*,5) wage (*,2) area
```

will result in:

variable	value	type
dept	ABCDEFGH	character
id	IJ	character
WAGE	12345	numeric
AREA	67	numeric

### **msym**

Specifies the character in the input file that is to be interpreted as a missing value. This example:

```
msym &;
```

defines the character ‘&’ as the missing value character. The default ‘.’ (dot) will always be interpreted as a missing value unless it is part of a numeric value.

### **nocheck**

Optional; suppresses automatic checking of packed ASCII record length and output data type. The default is to increase the record length by 2 bytes if the second record in a packed file starts with cr/lf, and any files that have explicitly defined character data will be output in double precision regardless of the type specified.

### **output**

The name of the **GAUSS** data set. A file will be created with the extension `.dat`. For example:

```
output /gauss/dat/test;
```

creates the file `test.dat` on the `/gauss/dat` directory.



outtyp

Selects the numerical accuracy of the output file. Use of this command should be dictated by the accuracy of the input data and storage space limitations. The format is:

```
outtyp fmt;
```

where *fmt* is:

- D or 8    double precision
- F or 4    single precision (default)
- I or 2    integer

The ranges of the different formats are:

bytes	data type	significant digits	range
2	integer	4	$-32768 \leq X \leq 32767$
4	single precision	6–7	$8.43 \times 10^{-37} \leq  X  \leq 3.37 \times 10^{+38}$
8	double precision	15–16	$4.19 \times 10^{-307} \leq  X  \leq 1.67 \times 10^{+308}$

If the output type is integer, the input numbers will be truncated to integers. If your data has more than 6 or 7 significant digits, specify **outtyp** as double.

Character data require **outtyp d**. ATOG automatically selects double precision when character data is specified in the **invar** statement, unless you have specified **nocheck**.

The precision of the storage selected does not affect the accuracy of **GAUSS** calculations using the data. **GAUSS** converts all data to double precision when the file is read.

outvar

Selects the variables to be placed in the **GAUSS** data set. The **outvar** command needs only the list of variables to be included in the output data set. They can be in any order. In this example:

```
invar $name #age pay $sex #var[1:10] x[005];  
outvar sex age x001 x003 var[1:8];
```

the **outvar** statement selects the following variables:

column	name	data type
1	sex	character
2	AGE	numeric
3	X001	numeric
4	X003	numeric
5	VAR01	numeric
6	VAR02	numeric
7	VAR03	numeric
8	VAR04	numeric
9	VAR05	numeric
10	VAR06	numeric
11	VAR07	numeric
12	VAR08	numeric

**outvar** is not used with packed ASCII files.

### **preserve case**

Optional; preserves the case of variable names. The default is **no preserve case**, which will force variable names for numeric variables to upper case and character variables to lower case.

## **23.3 Examples**

**Example 1** The first example is a soft delimited ASCII file called `agex1.asc`. The file contains seven columns of ASCII data:

```
Jan 167.3 822.4 6.34E06 yes 84.3 100.4
Feb 165.8 987.3 5.63E06 no 22.4 65.6
Mar 165.3 842.3 7.34E06 yes 65.4 78.3
```

The ATOG command file is `agex1.cmd`:

```
input /gauss/agex1.asc;
output agex1;
invar $month #temp pres vol $true var[02];
outvar month true temp pres vol;
```

The output data set will contain the following information:

name	month	true	TEMP	PRES	VOL
case 1	Jan	yes	167.3	822.4	6.34e+6
case 2	Feb	no	165.8	987.3	5.63e+6
case 3	Mar	yes	165.3	842.3	7.34e+6
type	char	char	numeric	numeric	numeric

The data set is double precision since character data is explicitly specified.

**Example 2** The second example is a packed ASCII file `xlod.asc`. The file contains 32-character records:

```

AEGDRFCSTy02345678960631567890<CR><LF>
EDJTAJPSTn12395863998064839561<CR><LF>
GWDNADMSTy19827845659725234451<CR><LF>
|           |           |           | | |
position 1      10      20      30 31 32
```

The ATOG command file is `xlod.cmd`:

```
input /gauss/dat/xlod.asc;  
output xlod2;  
invar record=32 $(1,3) client[2] zone (*,1) reg #(20,5) zip;
```

The output data set will contain the following information:

name	client1	client2	zone	reg	ZIP
case 1	AEG	DRF	CST	y	60631
case 2	EDJ	TAJ	PST	n	98064
case 3	GWD	NAD	MST	y	59725
type	char	char	char	char	numeric

The data set is double precision since character data is explicitly specified.

**Example 3** The third example is a hard delimited ASCII file called `cplx.asc`. The file contains six columns of ASCII data:

```
456.4, 345.2, 533.2, -345.5, 524.5, 935.3,  
-257.6, 624.3, 639.5, 826.5, 331.4, 376.4,  
602.3, -333.4, 342.1, 816.7, -452.6, -690.8
```

The ATOG command file is `cplx.cmd`:

```
input /gauss/cplx.asc;  
output cplx;  
invar delimit #cvar[3];  
complex;
```

The output data set will contain the following information:

name	cvar1		cvar2		cvar3
case 1	456.4	+ 345.2i	533.2	- 345.5i	524.5 + 935.3i
case 2	-257.6	+ 624.3i	639.5	+ 826.5i	331.4 + 376.4i
case 3	602.3	- 333.4i	342.1	+ 816.7i	-452.6 - 690.8i
type	numeric		numeric		numeric

The data set defaults to single precision, since no character data is present, and no **outtyp** command is specified.

## 23.4 Error Messages

### **atog - Can't find input file**

The ASCII input file could not be opened.

### **atog - Can't open output file**

The output file could not be opened.

### **atog - Can't open temporary file**

Notify Aptech Systems.

### **atog - Can't read temporary file**

Notify Aptech Systems.

### **atog - Character data in output file**

#### **Setting output file to double precision**

The output file contains character data. The type was set to double precision automatically.

### **atog - Character data longer than 8 bytes were truncated**

The input file contained character elements longer than 8 bytes. The conversion continued and the character elements were truncated to 8 bytes.

### **atog - Disk Full**

The output disk is full. The output file is incomplete.

### **atog - Found character data in numeric field**

This is a warning that character data was found in a variable that was specified as numeric. The conversion will continue.

**atog - Illegal command**

An unrecognizable command was found in a command file.

**atog - Internal error**

Notify Aptech Systems.

**atog - Invalid delimiter**

The delimiter following the backslash is not supported.

**atog - Invalid output type**

Output type must be I, F, or D.

**atog - Missing value symbol not found**

No missing value was specified in an **msym** statement.

**atog - No Input file**

No ASCII input file was specified. The **input** command may be missing.

**atog - No input variables**

No input variable names were specified. The **invar** statement may be missing.

**atog - No output file**

No output file was specified. The **output** command may be missing.

**atog - output type d required for character data  
Character data in output file will be lost**

Output file contains character data and is not double precision.

**atog - Open comment**

The command file has a comment that is not closed. Comments must be enclosed in @'s:

@ comment @

**atog - Out of memory**

Notify Aptech Systems.

**atog - read error**

A read error has occurred while converting a packed ASCII file.

**atog - Record length must be 1-16384 bytes**

The **record** subcommand has an out of range record length.

**atog - Statement too long**

Command file statements must be less than 16384 bytes.

**atog - Syntax error at:**

There is unrecognizable syntax in a command file.

**atog - Too many input variables**

More input variables were specified than available memory permitted.

**atog - Too many output variables**

More output variables were specified than available memory permitted.

**atog - Too many variables**

More variables were specified than available memory permitted.

**atog - Undefined variable**

A variable requested in an **outvar** statement was not listed in an **invar** statement.

**atog WARNING: missing ')' at:**

The parentheses in the **delimit** subcommand were not closed.

**atog WARNING: some records begin with cr/lf**

A packed ASCII file has some records that begin with a carriage return/linefeed. The record length may be wrong.

**atog - complex illegal for packed ASCII file.**

A **complex** command was encountered following an **invar** command with **record** specified.

**atog - Cannot read packed ASCII. (complex specified)**

An **invar** command with **record** specified was encountered following a **complex** command.



# Error Messages 24

The following is a list of error messages intrinsic to the **GAUSS** programming language. Error messages generated by library functions are not included here.

## **G0002 File too large**

<b>load</b>	Input file too large.
<b>getf</b>	Input file too large.

## **G0003 Indexing a matrix as a vector**

A single index can be used only on vectors. Vectors have only one row or only one column.

## **G0004 Compiler stack overflow - too complex**

An expression is too complex. Break it into smaller pieces. Notify Aptech Systems.

### **G0005 File is already compiled**

### **G0006 Statement too long**

Statement longer than 4000 characters.

### **G0007 End of file encountered**

### **G0008 Syntax error**

Compiler	Unrecognizable or incorrect syntax. Semicolon missing on previous statement.
<b>create</b>	Unrecognizable statement in command file, or <b>numvar</b> or <b>outvar</b> statement error.

### **G0009 Compiler pass out of memory**

Compiler pass has run out of memory. Notify Aptech Systems.

### **G0010 Can't open output file**

### **G0011 Compiled file must have correct extension**

GAUSS requires a .gcn extension.

### **G0012 Invalid drive specifier**

### **G0013 Invalid filename**

### **G0014 File not found**

### **G0015 Directory full**

### **G0016 Too many #include's**

**#include**'d files are nested too deep.

**G0017 WARNING: local outside of procedure**

A **local** statement has been found outside a procedure definition. The **local** statement will be ignored.

**G0018 Read error in program file****G0019 Can't edit .gcg file****G0020 Not implemented yet**

Command not supported in this implementation.

**G0021 use must be at the beginning of a program****G0022 User keyword cannot be used in expression****G0023 Illegal attempt to redefine symbol to an index variable****G0024 Invalid use of ->, probably should be .****G0025 Undefined symbol**

A symbol has been referenced that has not been given a definition.

**G0026 Too many symbols**

The global symbol table is full. (To set the limit, see **new** in the GAUSS LANGUAGE REFERENCE.)

**G0027 Invalid directory****G0028 Can't open configuration file**

GAUSS cannot find the configuration file.

### **G0029 Missing left parenthesis**

### **G0030 Insufficient workspace memory**

The space used to store and manipulate matrices and strings is not large enough for the operations attempted. (To make the main program space smaller and reclaim enough space to continue, see **new** in the GAUSS LANGUAGE REFERENCE.)

### **G0031 Execution stack too deep - expression too complex**

An expression is too complex. Break it into smaller pieces. Notify Aptech Systems.

### **G0032 fn function too large**

### **G0033 Missing right index bracket**

### **G0034 Missing arguments**

### **G0035 Argument too large**

### **G0036 Matrices are not conformable**

For a description of the function or operator being used and conformability rules, see MATRIX OPERATORS, Section 11.2, or the GAUSS LANGUAGE REFERENCE.

### **G0037 Result too large**

The size of the result of an expression is greater than the limit for a single matrix.

### **G0038 Not all the eigenvalues can be computed**

### **G0039 Matrix must be square to invert**

### **G0040 Not all the singular values can be computed**

### **G0041 Argument must be scalar**

A matrix argument was passed to a function that requires a scalar.

**G0042 Matrix must be square to compute determinant**

**G0043 Not implemented for complex matrices**

**G0044 Matrix must be real**

**G0045 Attempt to write complex data to real data set**

Data sets, unlike matrices, cannot change from real to complex after they are created.  
Use **create complex** to create a complex data set.

**G0046 Columns don't match**

The matrices must have the same number of columns.

**G0047 Rows don't match**

The matrices must have the same number of rows.

**G0048 Matrix singular**

The matrix is singular using the current tolerance.

**G0049 Target matrix not complex**

**G0050 Out of memory for program**

The main program area is full. (To increase the main program space, see **new** in the GAUSS LANGUAGE REFERENCE.)

**G0051 Program too large**

The main program area is full. (To increase the main program space, see **new** in the GAUSS LANGUAGE REFERENCE.)

**G0052 No square root - negative element**

### **G0053 Illegal index**

An illegal value has been passed in as a matrix index.

### **G0054 Index overflow**

An illegal value has been passed in as a matrix index.

### **G0055 retp outside of procedure**

A **retp** statement has been encountered outside a procedure definition.

### **G0056 Too many active locals**

The execution stack is full. There are too many local variables active. Restructure your program. Notify Aptech Systems.

### **G0057 Procedure stack overflow - expression too complex**

The execution stack is full. There are too many nested levels of procedure calls. Restructure your program. Notify Aptech Systems.

### **G0058 Index out of range**

You have referenced a matrix element that is out of bounds for the matrix being referenced.

### **G0059 exec command string too long**

### **G0060 Nonscalar index**

### **G0061 Cholesky downdate failed**

### **G0062 Zero pivot encountered**

<b>crout</b>	The Crout algorithm has encountered a diagonal element equal to 0. Use <b>croutp</b> instead.
--------------	---

**G0063 Operator missing**

An expression contains two consecutive operands with no intervening operator.

**G0064 Operand missing**

An expression contains two consecutive operators with no intervening operand.

**G0065 Division by zero!****G0066 Must be recompiled under current version**

You are attempting to use compiled code from a previous version of **GAUSS**. Recompile the source code under the current version.

**G0068 Program compiled under GAUSS-386 real version****G0069 Program compiled under GAUSS-386i complex version****G0070 Procedure calls too deep**

You may have a runaway recursive procedure.

**G0071 Type mismatch**

You are using an argument of the wrong data type (e.g., inputting a matrix when a string is called for).

**G0072 Too many files open**

The limit on simultaneously open files is 10.

**G0073 Redefinition of**

<b>declare</b>	An attempt has been made to initialize a variable that is already initialized. This is an error when <b>declare :=</b> is used. <b>declare !=</b> or <b>declare ?=</b> may be a better choice for your application.
----------------	---

<b>declare</b>	An attempt has been made to redefine a string as a matrix or procedure, or vice versa. delete the symbol and try again. If this happens in the context of a single program, you have a programming error. If this is a conflict between different programs, use a <b>new</b> statement before running the second program.
<b>let</b>	A string is being forced to type matrix. Use an <b>external matrix symbol</b> ; statement before the <b>let</b> statement.

**G0074 Can't run program compiled under GAUSS Light**

**G0075 gscroll input vector the wrong size**

**G0076 Call Aptech Systems Technical Support**

**G0077 New size cannot be zero**

You cannot **reshape** a matrix to a size of zero.

**G0078 vargetl outside of procedure**

**G0079 varputl outside of procedure**

**G0080 File handle must be an integer**

**G0081 Error renaming file**

**G0082 Error reading file**

**G0083 Error creating temporary file**

**G0084 Too many locals**

A procedure has too many local variables.



### **G0085 Invalid file type**

You cannot use this kind of file in this way.

### **G0086 Error deleting file**

### **G0087 Couldn't open**

The auxiliary output file could not be opened. Check the file name and make sure there is room on the disk.

### **G0088 Not enough memory to convert the whole string**

### **G0089 WARNING: duplicate definition of local**

### **G0090 Label undefined**

Label referenced has no definition.

### **G0091 Symbol too long**

Symbols can be no longer than 32 characters.

### **G0092 Open comment**

A comment was never closed.

### **G0093 Locate off screen**

### **G0094 Argument out of range**

### **G0095 Seed out of range**

### **G0096 Error parsing string**

**parse** encountered a token that was too long.

### **G0097 String not closed**

A string must have double quotes at both ends.

### **G0098 Invalid character for imaginary part of complex number**

### **G0099 Illegal redefinition of user keyword**

### **G0100 Internal E R R O R ###**

Notify Aptech Systems.

### **G0101 Argument cannot be zero**

The argument to **ln** or **log** cannot be zero.

### **G0102 Subroutine calls too deep**

Too many levels of **gosub**. Restructure your program.

### **G0103 return without gosub**

You have encountered a subroutine without executing a **gosub**.

### **G0104 Argument must be positive**

### **G0105 Bad expression or missing arguments**

Check the expression in question, or you forgot an argument.

### **G0106 Factorial overflow**

### **G0107 Nesting too deep**

Break the expression into smaller statements.

### **G0108 Missing left bracket [**

**G0109 Not enough data items**

You omitted data in a **let** statement.

**G0110 Found ) expected ] -****G0111 Found ] expected ) -****G0112 Matrix multiplication overflow****G0113 Unclosed (****G0114 Unclosed [****G0115 Illegal redefinition of function**

You are attempting to turn a function into a matrix or string. If this is a name conflict, **delete** the function.

**G0116 sysstate: invalid case****G0117 Invalid argument****G0118 Argument must be integer**

File handles must be integral.

**G0120 Illegal type for save****G0121 Matrix not positive definite**

The matrix is either not positive definite, or singular using the current tolerance.

**G0122 Bad file handle**

The file handle does not refer to an open file or is not in the valid range for file handles.

**G0123 File handle not open**

The file handle does not refer to an open file.

**G0124 readr call too large**

You are attempting to read too much in one call.

**G0125 Read past end of file**

You have already reached the end of the file.

**G0126 Error closing file****G0127 File not open for write****G0128 File already open****G0129 File not open for read****G0130 No output variables specified****G0131 Can't create file, too many variables****G0132 Can't write, disk probably full****G0133 Function too long****G0134 Can't seekr in this type of file****G0135 Can't seek to negative row****G0136 Too many arguments or misplaced assignment operator**

You have an assignment operator (=) where you want a comparison operator (==), or you have too many arguments.

**G0137** Negative argument - erf or erfc

**G0138** User keyword must have one argument

**G0139** Negative parameter - Incomplete Beta

**G0140** Invalid second parameter - Incomplete Beta

**G0141** Invalid third parameter - Incomplete Beta

**G0142** Nonpositive parameter - gamma

**G0143** NaN or missing value - cdfchic

**G0144** Negative parameter - cdfchic

**G0145** Second parameter < 1.0 - cdfchic

**G0146** Parameter too large - Incomplete Beta

**G0147** Bad argument to trig function

**G0148** Angle too large to trig function

**G0149** Matrices not conformable

For a description of the function or operator being used and conformability rules, see  
MATRIX OPERATORS, Section 11.2, or the GAUSS LANGUAGE REFERENCE.

**G0150** Matrix not square

**G0151** Sort failure

### **G0152 Variable not initialized**

You have referenced a variable that has not been initialized to any value.

### **G0153 Unsuccessful close on auxiliary output**

The disk may be full.

### **G0154 Illegal redefinition of string**

### **G0155 Nested procedure definition**

A **proc** statement was encountered inside a procedure definition.

### **G0156 Illegal redefinition of procedure**

You are attempting to turn a procedure into a matrix or string. If this is a name conflict, delete the procedure.

### **G0157 Illegal redefinition of matrix**

### **G0158 endp without proc**

You are attempting to end a procedure that you never started.

### **G0159 Wrong number of parameters**

You called a procedure with the wrong number of arguments.

### **G0160 Expected string variable**

### **G0161 User keywords return nothing**

### **G0162 Can't save proc/keyword/fn with global references**

Remove the global references or leave this in source code form for the autoloader to handle. (See **library** in the GAUSS LANGUAGE REFERENCE.)

**G0163 Wrong size format matrix**

**G0164 Bad mask matrix**

**G0165 Type mismatch or missing arguments**

**G0166 Character element too long**

The maximum length for character elements is 8 characters.

**G0167 Argument must be column vector**

**G0168 Wrong number of returns**

The procedure was defined to return a different number of items.

**G0169 Invalid pointer**

You are attempting to call a local procedure using an invalid procedure pointer.

**G0170 Invalid use of ampersand**

**G0171 Called symbol is wrong type**

You are attempting to call a local procedure using a pointer to something else.

**G0172 Can't resize temporary file**

**G0173 varindx failed during open**

The global symbol table is full.

**G0174 ‘.’ and ‘ ’ operators must be inside [ ] brackets**

These operators are for indexing matrices.

**G0175 String too long to compare**

**G0176 Argument out of range**

**G0177 Invalid format string**

**G0178 Invalid mode for getf**

**G0179 Insufficient heap space**

**G0180 Trim too much**

You are attempting to trim more rows than the matrix has.

**G0181 Illegal assignment - type mismatch**

**G0182 2nd and 3rd arguments different order**

**G0274 Invalid parameter for conv**

**G0275 Parameter is NaN (Not A Number)**

The argument is a NaN (see SPECIAL DATA TYPES, Section [10.6.8](#)).

**G0276 Illegal use of reserved word**

**G0277 Null string illegal here**

**G0278 proc without endp**

You must terminate a procedure definition with an **endp** statement.

**G0286 Multiple assign out of memory**

**G0287 Seed not updated**



The seed argument to **rndns** and **rndus** must be a simple local or global variable reference. It cannot be an expression or constant. These functions are obsolete, please use **rndlcu** and **rndlcu**

**G0288 Found break not in do loop**

**G0289 Found continue not in do loop**

**G0290 Library not found**

The specified library cannot be found on the **lib\_path** path. Make sure installation was correct.

**G0291 Compiler pass out of memory**

Notify Aptech Systems.

**G0292 File listed in library not found**

A file listed in a library could not be opened.

**G0293 Procedure has no definition**

The procedure was not initialized. Define it.

**G0294 Error opening temporary file**

One of the temporary files could not be opened. The directory may be full.

**G0295 Error writing temporary file**

One of the temporary files could not be written to. The disk may be full.

**G0296 Can't raise negative number to nonintegral power**

**G0300 File handle must be a scalar**

**G0301 Syntax error in library**

### **G0302 File has been truncated or corrupted**

<b>getname</b>	File header cannot be read.
<b>load</b>	Cannot read input file, or file header cannot be read.
<b>open</b>	File size does not match header specifications, or file header cannot be read.

### **G0317 Can't open temp file**

### **G0336 Disk full**

### **G0339 Can't debug compiled program**

### **G0341 File too big**

### **G0347 Can't allocate that many globals**

### **G0351 Warning: Not reinitializing : declare ?=**

The symbol is already initialized. It will be left as is.

### **G0352 Warning: Reinitializing : declare !=**

The symbol is already initialized. It will be reset.

### **G0355 Wrong size line matrix**

### **G0360 Write error**

### **G0364 Paging error**

### **G0365 Unsupported executable file type**

**G0368 Unable to allocate translation space**

**G0369 Unable to allocate buffer**

**G0370 Syntax Error in code statement**

**G0371 Syntax Error in recode statement**

**G0372 Token verify error**

Notify Aptech Systems.

**G0373 Procedure definition not allowed**

A procedure name appears on the left side of an assignment operator.

**G0374 Invalid make statement**

**G0375 make Variable is a Number**

**G0376 make Variable is Procedure**

**G0377 Cannot make Existing Variable**

**G0378 Cannot make External Variable**

**G0379 Cannot make String Constant**

**G0380 Invalid vector statement**

**G0381 vector Variable is a Number**

**G0382 vector Variable is Procedure**

**G0383 Cannot vector Existing Variable**

**G0384 Cannot vector External Variable**

**G0385 Cannot vector String Constant**

**G0386 Invalid extern statement**

**G0387 Cannot extern number**

**G0388 Procedures always external**

A procedure name has been declared in an **extern** statement. This is a warning only.

**G0389 extern variable already local**

A variable declared in an **extern** statement has already been assigned local status.

**G0390 String constant cannot be external**

**G0391 Invalid code statement**

**G0392 code Variable is a Number**

**G0393 code Variable is Procedure**

**G0394 Cannot code Existing Variable**

**G0395 Cannot code External Variable**

**G0396 Cannot code String Constant**

**G0397 Invalid recode statement**

**G0398 recode Variable is a Number**

**G0399 recode Variable is Procedure**

**G0400 Cannot recode External Variable**

**G0401 Cannot recode String Constant**

**G0402 Invalid keep statement**

**G0403 Invalid drop statement**

**G0404 Cannot define Number**

**G0405 Cannot define String**

**G0406 Invalid select statement**

**G0407 Invalid delete statement**

**G0408 Invalid outtyp statement**

**G0409 outtyp already defaulted to 8**

Character data has been found in the output data set before an **outtyp 2** or **outtyp 4** statement. This is a warning only.

**G0410 outtyp must equal 2, 4, or 8**

**G0411 outtyp override...precision set to 8**

Character data has been found in the output data set after an **outtyp 2** or **outtyp 4** statement. This is a warning only.

**G0412 default not allowed in recode statement**

`default` allowed only in `code` statement.

**G0413 Missing file name in dataloop statement**

**G0414 Invalid listwise statement**

**G0415 Invalid lag statement**

**G0416 lag variable is a number**

**G0417 lag variable is a procedure**

**G0418 Cannot lag External Variable**

**G0419 Cannot lag String Constant**

**G0421 Command not supported in Run-Time Module**

**G0428 Cannot use debug command inside program**

**G0429 Invalid number of subdiagonals**

**G0431 Error closing dynamic library**

**G0432 Error opening dynamic library**

**G0433 Cannot find DLL function**

**G0434 Error opening default dynamic library**

**G0435 Invalid mode**

G0436 Matrix is empty

G0437 loadexe not supported; use dlibrary instead

G0438 callexe not supported; use dllcall instead

G0439 File has wrong bit order

G0440 File has wrong byte order

G0441 Type vector malloc failed

G0442 No type vector in gfblock

G0445 Illegal left-hand side reference in procedure

G0446 Argument is the wrong size

G0447 vfor called with illegal loop level

G0454 Failure opening printer for output

G0456 Failure buffering output for printer

G0457 Cannot take log of a negative number

G0458 Attempt to index proc/fn/keyword as a matrix

G0459 Missing right brace

G0460 Unexpected end of statement

G0461 Too many data items

G0462 Negative trim value

G0463 Failure generating graph

G0465 Redefinition of structure, number of elements

G0466 Redefinition of structure, type mismatch

G0467 Redefinition of structure, unrecognized member

G0468 Structure definition inside procedure definition

G0469 Cannot create translator temp file

G0470 Symbol not found

G0472 Invalid name

G0473 String not terminated with null byte

G0477 FOR loops nested too deep

G0486 Character argument too long

G0487 License expired

G0490 License manager initialization error

G0491 License manager error



G0492 Licensing failure

G0497 Missing right parenthesis

G0500 Cannot create temporary filename

G0503 Cannot assign matrix to scalar member

G0504 Invalid structure member

G0505 Invalid structure redefinition

G0506 Structure assignment mismatch

G0507 Undefined structure

G0508 Structure argument mismatch

G0509 Too many structure members

G0510 Duplicate name for structure member

G0514 Not supported for structures

G0515 Too many values in locator

G0516 Too many dimensions in result

G0517 Too many dimensions in argument

G0518 Not implemented for complex

G0519 Illegal dereference of structure array

G0520 Arguments not conformable

G0521 Argument must be real

G0522 Illegal indexing of dereferenced structure

G0523 Numeric argument must be integer

G0524 Found comma, expecting index

G0525 Argument contains NaNs

G0526 Argument must be compact format

G0529 Array orders must be  $\geq 1$

G0531 Two trailing dimensions of argument must be the same size

G0532 Both dimensions of argument must be the same size

G0533 1-dimensional argument must contain only 1 element

G0534 Cannot create file

G0538 Zero illegal in for loop increment

G0541 Illegal assignment to FOR loop counter

G0542 Object too large for 32-bit version

G0543 Array has too many dimensions for matrix assign

G0547 Array not conformable for indexing

G0548 Array not conformable for boolean operation

G0549 Global structure pointer cannot point to local structure

G0550 Invalid use of \*

G0551 Feature not authorized

G0553 Path too long



# Maximizing Performance 25

These hints will help you maximize the performance of your new **GAUSS** System.

## 25.1 Library System

Some temporary files are created during the autoloading process. If you have a **tmp\_path** configuration variable or a **tmp** environment string that defines a path on a RAM disk, the temporary files will be placed on the RAM disk.

For example:

```
set tmp=f:\tmp
```

**tmp\_path** takes precedence over the **tmp** environment variable.

A disk cache will also help, as well as having your frequently used files in the first path in the **src\_path**.

You can optimize your library .lcn files by putting the correct drive and path on each file name listed in the library. The **lib** command will do this for you.

Use the **compile** command to precompile your large frequently used programs. This will completely eliminate compile time when the programs are rerun.

## 25.2 Loops

The use of the built-in matrix operators and functions rather than **do** loops will ensure that you are utilizing the potential of **GAUSS**.

Here is an example:

Given the vector **x** with 8000 normal random numbers,

```
x = rndn(8000,1);
```

you could get a count of the elements with an absolute value greater than 1 with a **do** loop, like this:

```
c = 0;
i = 1;
do while i <= rows(x);
    if abs(x[i]) > 1;
        c = c+1;
    endif;
    i = i+1;
endo;
print c;
```

Or, you could use:

```
c = sumc(abs(x) .> 1);
print c;
```

The **do** loop takes over 40 times longer.

## 25.3 Memory Usage

Computers today can have large amounts of RAM. This doesn't mean that large data sets should be read entirely into memory. Many **GAUSS** procedures and applications are written to allow for data sets to be read in sections rather than all at once. Even if you have enough RAM to store the data set completely, you should consider taking advantage of this feature. The speed-ups using this feature can be significant. For example, **ols** is called using a data set stored in a matrix versus stored on the disk in a **GAUSS** data set. The computer is a 2.8 Megahertz computer with Windows XP.

```
y = rndn(250000,1);
x = rndn(250000,100);
xlbl = 0$+"X"+ftocv(seqa(1,1,100),1,0);
lbl = "Y" | xlbl;
call saved(y~x,"test",lbl);

__output = 0;
t0 = date;
call ols("",y,x);
t1 = date;
t2 = date;
call ols("test","Y",xlabel);
t3 = date;
print ethsec(t2,t3)/100 " seconds;
print;
print ethsec(t0,t1)/100 " seconds";

25.750000 seconds
9.6720000 seconds
```

This represents more than a 50% speedup by leaving the data on the disk.

### **maxvec,maxbytes**

**maxvec** is a **GAUSS** procedure that returns the value of the global variable **\_\_maxvec** that determines the amount of data to be read in at a time from a **GAUSS** data set. This value can be modified for a particular run by setting **\_\_maxvec** in your command file to some other value. The value returned by a call to **maxvec** can be permanently modified by editing **system.dec** and changing the value of **\_\_maxvec**. The value returned when running **GAUSS Light** is always 8192.

**maxbytes** is a **GAUSS** procedure that returns the value of a scalar global **\_\_maxbytes** that sets the amount of available RAM. This value can be modified for a particular run by setting **\_\_maxbytes** in your command file to some other value. The value returned by a call to **maxbytes** can be permanently modified by editing **system.dec** and changing the value of **\_\_maxbytes**.

If you wish to force **GAUSS** procedures and applications to read a **GAUSS** data set in its entirety, set **\_\_maxvec** and **\_\_maxbytes** to very large values.

### **25.3.1 Hard Disk Maintenance**

The hard disk used for the swap file should be optimized occasionally with a disk optimizer. Use a disk maintenance program to ensure that the disk media is in good shape.

### **25.3.2 CPU Cache**

There is a line for cache size in the **gauss.cfg** file. Set it to the size of the CPU data cache for your computer.

This affects the choice of algorithms used for matrix multiply functions.

This will not change the results you get, but it can radically affect performance for large matrices.



# Fonts A

There are four fonts available in the **Publication Quality Graphics** System:

Simplex	standard sans serif font
Simgrma	Simplex greek, math
Microb	bold and boxy
complex	standard font with serif

The following tables show the characters available in each font and their ASCII values. (For details on selecting fonts for your graph, see **SELECTING FONTS**, Section [22.4.1](#).

## A.1 Simplex

33	!	61	=	89	Y	117	u
34	"	62	>	90	Z	118	v
35	#	63	?	91	[	119	w
36	\$	64	@	92	\	120	x
37	%	65	A	93	]	121	y
38	&	66	B	94	^	122	z
39	'	67	C	95	_	123	{
40	(	68	D	96	'	124	
41	)	69	E	97	a	125	}
42	*	70	F	98	b	126	~
43	+	71	G	99	c		
44	,	72	H	100	d		
45	-	73	I	101	e		
46	.	74	J	102	f		
47	/	75	K	103	g		
48	0	76	L	104	h		
49	1	77	M	105	i		
50	2	78	N	106	j		
51	3	79	O	107	k		
52	4	80	P	108	l		
53	5	81	Q	109	m		
54	6	82	R	110	n		
55	7	83	S	111	o		
56	8	84	T	112	p		
57	9	85	U	113	q		
58	:	86	V	114	r		
59	;	87	W	115	s		
60	<	88	X	116	t		

## A.2 Simgrma

33	$\epsilon$	61	$\neq$	89	$\psi$	117	$\simeq$
34	$($	62	$\geq$	90	$\approx$	118	$)$
35	$\equiv$	63	$\simeq$	91	$[$	119	$\omega$
36	$\approx$	64	$\cup$	92	$\partial$	120	$\xi$
37	$\uparrow$	65	$\frac{1}{2}$	93	$]$	121	$\psi$
38	$\sqrt{\phantom{x}}$	66	$\frac{1}{3}$	94	$\cap$	122	$\zeta$
39	$\prime$	67	$H$	95	$\downarrow$	123	$\}$
40	$\subset$	68	$\Delta$	96	$\sim$	124	$\int$
41	$\supset$	69	$\frac{1}{8}$	97	$\alpha$	125	$\}$
42	$\times$	70	$\Phi$	98	$\beta$	126	$\infty$
43	$\pm$	71	$\Gamma$	99	$\eta$		
44	$\int$	72	$X$	100	$\delta$		
45	$\mp$	73	$\frac{2}{3}$	101	$\varepsilon$		
46	$\cdot$	74	$\perp$	102	$\varphi$		
47	$\div$	75	$\frac{3}{8}$	103	$\gamma$		
48	$\nabla$	76	$\wedge$	104	$\chi$		
49	$\sqrt{\phantom{x}}$	77	$\frac{5}{8}$	105	$\iota$		
50	$\phi$	78	$\frac{7}{8}$	106	$t$		
51	$<$	79	$\frac{1}{4}$	107	$\kappa$		
52	$>$	80	$\Pi$	108	$\lambda$		
53	$/$	81	$\Theta$	109	$\mu$		
54	$\exists$	82	$P$	110	$\nu$		
55	$\parallel$	83	$\Sigma$	111	$o$		
56	$\infty$	84	$\lesssim$	112	$\pi$		
57	$\odot$	85	$\Upsilon$	113	$\vartheta$		
58	$\rightarrow$	86	$\leftrightarrow$	114	$\rho$		
59	$\leftarrow$	87	$\Omega$	115	$\sigma$		
60	$\cong$	88	$\Xi$	116	$\tau$		

### A.3 Microb

33	!	61	=	89	Y	117	u
34	"	62	>	90	Z	118	v
35	#	63	?	91	[	119	w
36	\$	64	@	92	\	120	x
37	%	65	A	93	]	121	y
38	&	66	B	94	^	122	z
39	'	67	C	95	_	123	{
40	[	68	D	96	`	124	
41	]	69	E	97	a	125	}
42	*	70	F	98	b	126	~
43	+	71	G	99	c		
44	,	72	H	100	d		
45	-	73	I	101	e		
46	.	74	J	102	f		
47	/	75	K	103	g		
48	0	76	L	104	h		
49	1	77	M	105	i		
50	2	78	N	106	j		
51	3	79	O	107	k		
52	4	80	P	108	l		
53	5	81	Q	109	m		
54	6	82	R	110	n		
55	7	83	S	111	o		
56	8	84	T	112	p		
57	9	85	U	113	q		
58	:	86	V	114	r		
59	;	87	W	115	s		
60	<	88	X	116	t		

## A.4 Complex

33	!	61	=	89	Y	117	u
34	"	62	>	90	Z	118	v
35	#	63	?	91	[	119	w
36	\$	64	@	92	\	120	x
37	%	65	A	93	]	121	y
38	&	66	B	94	^	122	z
39	'	67	C	95	_	123	{
40	(	68	D	96	`	124	
41	)	69	E	97	a	125	}
42	*	70	F	98	b	126	~
43	+	71	G	99	c		
44	,	72	H	100	d		
45	-	73	I	101	e		
46	.	74	J	102	f		
47	/	75	K	103	g		
48	0	76	L	104	h		
49	1	77	M	105	i		
50	2	78	N	106	j		
51	3	79	O	107	k		
52	4	80	P	108	l		
53	5	81	Q	109	m		
54	6	82	R	110	n		
55	7	83	S	111	o		
56	8	84	T	112	p		
57	9	85	U	113	q		
58	:	86	V	114	r		
59	;	87	W	115	s		
60	<	88	X	116	t		



# Reserved Words Appendix B

The following words are used for **GAUSS** functions. You cannot use these names for variables or procedures in your programs:

## A

<code>abs</code>	<code>AmericanBSCall</code>
<code>acf</code>	<code>AmericanBSCall_Greeks</code>
<code>concat</code>	<code>AmericanBSCall_ImpVol</code>
<code>acos</code>	<code>AmericanBSPut</code>
<code>aeye</code>	<code>AmericanBSPut_Greeks</code>
<code>amax</code>	<code>AmericanBSPut_ImpVol</code>
<code>amean</code>	<code>amin</code>
<code>AmericanBinomCall</code>	<code>amult</code>
<code>AmericanBinomCall_Greeks</code>	<code>and</code>
<code>AmericanBinomCall_ImpVol</code>	<code>annualTradingDays</code>
<code>AmericanBinomPut</code>	<code>arccos</code>
<code>AmericanBinomPut_Greeks</code>	<code>arcsin</code>
<code>AmericanBinomPut_ImpVol</code>	<code>arctan</code>

arctan2  
areshape  
arrayalloc  
arrayindex  
arrayinit  
arraytomat  
asclabel

asin  
asum  
atan  
atan2  
atranspose  
axmargin

## B

balance  
band  
bandchol  
bandcholsol  
bandltsol  
bandrv  
bandsolpd  
bar

base10  
begwind  
besselj  
bessely  
box  
boxcox  
break

## C

calcbox  
call  
callexe  
cdfbeta  
cdfbvn  
cdfbvn2  
cdfbvn2e  
cdfchic  
cdfchii  
cdfchinc  
cdffc  
cdffnc  
cdfgam

cdfmvn  
cdfn  
cdfn2  
cdfnc  
cdfni  
cdftc  
cdftci  
cdftnc  
cdftvn  
cdir  
ceil  
cfft  
cfft\_i



changedir	conj
chdir	cons
checkinterrupt	continue
chol	contour
choldn	conv
cholsol	convertsatostr
cholup	convertstrtosa
chrs	coreleft
cint	corrm
clear	corrms
clearg	corrvc
close	corrxx
closeall	corrxs
cls	cos
cmsplit	cosh
cmsplit2	counts
code	countwts
color	create
cols	crossprd
colsf	crout
combinate	croutp
combined	csrcol
comlog	csrln
commandeerm	csrtype
commandeersa	cumprodc
compile	cumsumc
complex	curve
con	cvtos
cond	cvtosa
conformed	

## D

datacreate	datalist
datacreatecomplex	dataload

dataopen	dotfeq
datasave	dotfeqmt
date	dotfge
datestr	dotfgemt
datestring	dotfgt
datestrymd	dotfgtmt
dayinyr	dotfle
dayOfWeek	dotflemt
debug	dotflt
declare	dotflmt
delete	dotfne
deletefile	dotfnemt
delif	draw
denseSubmat	dsCreate
design	dstat
det	dstatmt
detl	dstatmtControlCreate
dfft	dtdate
dffti	dtday
dfree	dttime
diag	dttodtv
diagrv	dttostr
digamma	dttoutc
disable	dtvnormal
dlibrary	dtvtodt
dllcall	dtvtoutc
do	dummy
dos	dummybr
doswincloseall	dummydn
doswinopen	

## E

ed	editm
edit	eig

eigcg	eqSolveSet
eigcg2	eqv
eigch	erf
eigch2	erfc
eigh	error
eighv	errorlog
eigr	etdays
eigr2	ethsec
eigrs	etstr
eigrs2	EuropeanBinomCall
eigv	EuropeanBinomCall_Greeks
elapsedTradingDays	EuropeanBinomCall_ImpVol
else	EuropeanBinomPut
elseif	EuropeanBinomPut_Greeks
enable	EuropeanBinomPut_ImpVol
end	EuropeanBSCall
endfor	EuropeanBSCall_Greeks
endif	EuropeanBSCall_ImpVol
endo	EuropeanBSPut
endp	EuropeanBSPut_Greeks
endwind	EuropeanBSPut_ImpVol
envget	exctsmpl
eof	exec
eq	execbg
eqSolve	exp
eqSolvemt	expr
eqSolvemtControlCreate	external
eqSolvemtOutCreate	eye

## F

fcheckerr	fflush
fclearerr	fft
feq	ffti
feqmt	fftm

fftmi	fne
fftn	fnemt
fge	font
fgemt	fontload
fgets	fonts
fgetsa	fontunload
fgetsat	fontunloadall
fgetst	fopen
fgt	for
fgtmt	format
fileinfo	formatcv
files	formatnv
filesa	fputs
fix	fputst
fle	fseek
flemt	fstrerror
floor	ftell
flt	ftocv
fltmt	ftos
fmod	ftostrc
fn	

## G

gamma	gdagetype
gammaii	gdagetypes
gausset	gdagetvarinfo
gdaappend	gdaiscplx
gdacreate	gdapack
gdadstat	gdaread
gdadstatmat	gdareadbyindex
gdagetindex	gdareadsome
gdagetname	gdareportvarinfo
gdagetnames	gdaupdate
gdagetorders	gdaupdateandpack

gdawrite  
gdawritesome  
gdtfastcat  
ge  
getarray  
getdims  
getf  
getmatrix  
getmatrix4d  
getname  
getnamef  
getNextTradingDay  
getNextWeekDay  
getnr  
getnrmt  
getorders  
getpath

getPreviousTradingDay  
getPreviousWeekDay  
getscalar3d  
getscalar4d  
getwind  
gosub  
goto  
gradMT  
gradMTm  
gradp  
graph  
graphgpg  
graphinit  
graphprt  
graphset  
graphsev3  
gt

## H

hardcopy  
hasimag  
header  
headermt  
hess  
hessMT  
hessMTg  
hessMTgw

hessMTm  
hessMTmw  
hessMTw  
hessp  
hist  
histf  
histp  
hsec

## I

if  
imag  
indcv

indexcat  
indices  
indices2

<code>indicesf</code>	<code>intquad3</code>
<code>indicesfn</code>	<code>intrleav</code>
<code>indnv</code>	<code>intrleavsa</code>
<code>indsav</code>	<code>intrsect</code>
<code>int</code>	<code>intrsectsa</code>
<code>intgrat2</code>	<code>intsimp</code>
<code>intgrat3</code>	<code>inv</code>
<code>inthp</code>	<code>invpd</code>
<code>intHP1</code>	<code>invswp</code>
<code>intHP2</code>	<code>iscplx</code>
<code>intHP3</code>	<code>iscplx</code>
<code>intHP4</code>	<code>isinfnanmiss</code>
<code>inthpControlCreate</code>	<code>issmiss</code>
<code>intquad1</code>	<code>isSparse</code>
<code>intquad2</code>	

## K

<code>key</code>	<code>keyw</code>
<code>keyav</code>	<code>keyword</code>
<code>keymatchmc</code>	

## L

<code>lag</code>	<code>lapgeigv</code>
<code>lag1</code>	<code>lapgschur</code>
<code>lag</code>	<code>lapgsvdcst</code>
<code>lapeighb</code>	<code>lapgsvds</code>
<code>lapeighi</code>	<code>lapgsvdst</code>
<code>lapeighvb</code>	<code>lapsvdcusv</code>
<code>lapeighvi</code>	<code>lapsvds</code>
<code>lapgeig</code>	<code>lapsvdusv</code>
<code>lapgeigh</code>	<code>le</code>
<code>lapgeighv</code>	<code>let</code>

lib	loadp
library	loads
license_id	loadstruct
line	loadwind
linsolve	local
ln	locate
lncdfbvn	loess
lncdfbvn2	loessmt
lncdfmvn	loessmtControlCreate
lncdfn	log
lncdfn2	loglog
lncdfnc	logx
lnfact	logy
lngamma	loopnextindex
lnpdfmvn	lower
lnpdfmvt	lowmat
lnpdfn	lowmat1
lnpdft	lpos
load	lprint
loadarray	lpwidth
loadd	lshow
loadexe	lt
loadf	ltrisol
loadk	lu
loadm	lusol

**M**

machEpsilon	mattoarray
makevars	maxbytes
makewind	maxc
margin	maxindc
matalloc	maxvec
matinit	mbesselei
matrix	mbesselei0

<b>mbesselei1</b>	<b>minindc</b>
<b>mbesseli</b>	<b>miss</b>
<b>mbesseli0</b>	<b>missex</b>
<b>mbesseli1</b>	<b>missrv</b>
<b>meanc</b>	<b>moment</b>
<b>median</b>	<b>momentd</b>
<b>mergeby</b>	<b>movingave</b>
<b>mergebysa</b>	<b>movingaveExpwgt</b>
<b>mergevar</b>	<b>movingaveWgt</b>
<b>minc</b>	<b>msym</b>

## N

<b>nametype</b>	<b>nextn</b>
<b>ndpchk</b>	<b>nextnevn</b>
<b>ndpclex</b>	<b>nextwind</b>
<b>ndpcntrl</b>	<b>not</b>
<b>ne</b>	<b>null</b>
<b>new</b>	<b>null1</b>
<b>nextindex</b>	<b>numCombinations</b>

## O

<b>oldfft</b>	<b>open</b>
<b>oldffti</b>	<b>openpqg</b>
<b>ols</b>	<b>optn</b>
<b>olsmt</b>	<b>optnevn</b>
<b>olsmtControlCreate</b>	<b>or</b>
<b>olsqr</b>	<b>orth</b>
<b>olsqr2</b>	<b>output</b>
<b>olsqrmt</b>	<b>outwidth</b>
<b>ones</b>	



---

**P**

pacf	printfm
packr	printfmt
parse	proc
pause	prodc
pdfn	push
pi	putarray
pinv	putf
pinvmt	pvCreate
plot	pvgetIndex
plotsym	pvgetparnames
polar	pvgetparvector
polychar	pvLength
polyeval	pvList
polyint	pvnumoffsets
polymake	pvoffsets
polymat	pvPack
polymroot	pvPacki
polymult	pvPackm
polyroot	pvPackmi
pop	pvPacks
pqgwin	pvPacksi
prcsn	pvPacksm
previousindex	pvPacksmi
princomp	pvputparvector
print	pvtest
printdos	pvunpack

**Q**

QNewton	qnewtonset
QNewtonmt	QProg
QNewtonmtControlCreate	QProgmt
QNewtonmtOutCreate	qprogMTInCreate

qqr	qtyre
qqre	qtyrep
qqrep	quantile
qr	quantiled
qre	quantilem
qrep	quantilemd
qrsol	qyr
qrtsol	qyre
qtyr	qyrep

## R

rank	rfftnp
rankindx	rfftp
readr	rndbeta
real	rndcon
recode	rndgam
recserar	rndi
recsercp	rndKMbeta
recserrc	rndKMgam
register_off	rndkmi
register_on	rndkmm
register_reset	rndKMnb
register_show	rndKMp
renamefile	rndkmu
replay	rndKMvm
rerun	rndLCbeta
reshape	rndLCgam
retp	rndlci
return	rndlcn
rev	rndLCnb
rfft	rndLCp
rffti	rndlcu
rfftip	rndLCvm
rfftn	rndmod

`rndmult`  
`rndn`  
`rndnb`  
`rndns`  
`rndp`  
`rndseed`  
`rndu`  
`rndus`

`rndvm`  
`rotater`  
`round`  
`rows`  
`rowsf`  
`rref`  
`run`

## S

`satocv`  
`satostrC`  
`save`  
`saveall`  
`saved`  
`savestruct`  
`savewind`  
`scale`  
`scale3d`  
`scalerr`  
`scalinfnanmiss`  
`scalmiss`  
`schtoc`  
`schur`  
`screen`  
`scroll`  
`searchsourcepath`  
`seekr`  
`selif`  
`seqa`  
`seqm`  
`setarray`  
`setcnvrt`  
`setdif`

`setdifsa`  
`setvars`  
`setvmode`  
`setvwrmode`  
`setwind`  
`shell`  
`shiftr`  
`show`  
`showpqq`  
`sin`  
`singleindex`  
`sinh`  
`sleep`  
`solpd`  
`sortc`  
`sortcc`  
`sortd`  
`sorthc`  
`sorthcc`  
`sortind`  
`sortindc`  
`sortindmc`  
`sortmc`  
`sortr`

<b>sortrc</b>	<b>strindx</b>
<b>sparseCols</b>	<b>string</b>
<b>sparseEye</b>	<b>strlen</b>
<b>sparseFD</b>	<b>strput</b>
<b>sparseFP</b>	<b>strrindx</b>
<b>sparseHConcat</b>	<b>strsect</b>
<b>sparseNZE</b>	<b>strsplit</b>
<b>sparseOnes</b>	<b>strsplitpad</b>
<b>sparseRows</b>	<b>strtodt</b>
<b>sparseScale</b>	<b>strtodtd</b>
<b>sparseSet</b>	<b>strttof</b>
<b>sparseSolve</b>	<b>strttofcplx</b>
<b>sparseSubmat</b>	<b>strtriml</b>
<b>sparseTD</b>	<b>strtrimr</b>
<b>sparseTranspose</b>	<b>strtrunc</b>
<b>sparseTrTD</b>	<b>strtrunc1</b>
<b>sparseTscalar</b>	<b>strtruncpad</b>
<b>sparseVConcat</b>	<b>strtruncr</b>
<b>spline</b>	<b>struct</b>
<b>spline1D</b>	<b>submat</b>
<b>spline2D</b>	<b>subscat</b>
<b>sqpmt_feasible</b>	<b>substute</b>
<b>sqpmt_meritFunct</b>	<b>subvec</b>
<b>sqpSolve</b>	<b>sumc</b>
<b>SQPsolveMT</b>	<b>sumr</b>
<b>sqpSolveMTcontrolCreate</b>	<b>surface</b>
<b>sqpSolveMTlagrangeCreate</b>	<b>svd</b>
<b>sqpSolveMToutCreate</b>	<b>svd1</b>
<b>sqpSolveset</b>	<b>svd2</b>
<b>sqrt</b>	<b>svdcusv</b>
<b>stdc</b>	<b>svds</b>
<b>stocv</b>	<b>svdusv</b>
<b>stof</b>	<b>sysstate</b>
<b>stop</b>	<b>system</b>
<b>strcombine</b>	

## T

tab	toeplitz
tan	token
tanh	topolar
tempname	trace
time	trap
timedt	trapchk
timestr	trigamma
timeutc	trim
title	trimr
tkf2eps	trunc
tkf2ps	type
tkf2ps_margin	typecv
tocart	typef
todaydt	

## U

union	until
unionsa	upmat
uniqindmc	upmat1
uniqindx	upper
uniqindxsa	use
unique	utctodt
uniquemc	utctodtv
uniquesa	utrisol

## V

vals	varmares
varget	varput
vargetl	varputl
varmall	vartype

<b>vartypef</b>	<b>vget</b>
<b>vcm</b>	<b>view</b>
<b>vcms</b>	<b>viewxyz</b>
<b>vcx</b>	<b>vlist</b>
<b>vcxs</b>	<b>vnamecv</b>
<b>vec</b>	<b>volume</b>
<b>vech</b>	<b>vput</b>
<b>vecr</b>	<b>vread</b>
<b>vfor</b>	<b>vtypecv</b>

## W

<b>wait</b>	<b>winpan</b>
<b>waitc</b>	<b>winprint</b>
<b>walkindex</b>	<b>winprintpqq</b>
<b>while</b>	<b>winrefresh</b>
<b>winclear</b>	<b>winrefresharea</b>
<b>wincleararea</b>	<b>winresize</b>
<b>winclearttylog</b>	<b>winsetactive</b>
<b>winclose</b>	<b>winsetbackground</b>
<b>wincloseall</b>	<b>winsetcolor</b>
<b>winconvertpqq</b>	<b>winsetcolorcells</b>
<b>window</b>	<b>winsetcolormap</b>
<b>wingetactive</b>	<b>winsetcursor</b>
<b>wingetattributes</b>	<b>winsetforeground</b>
<b>wingetcolorcells</b>	<b>winsetrefresh</b>
<b>wingetcursor</b>	<b>winsetttextwrap</b>
<b>winmove</b>	<b>winwrite</b>
<b>winopenpqq</b>	<b>winzoompqq</b>
<b>winopentext</b>	<b>writer</b>
<b>winopentty</b>	

X

x_indcv	xtics
xlabel	xy
xor	xyz
xpnd	

Y

ylabel	ytics
--------	-------

Z

zeros	ztics
zlabel	





# Singularity Tolerance Appendix

# C

The tolerance used to determine whether or not a matrix is singular can be changed. The default value is  $1.0\text{e-}14$  for both the LU and the Cholesky decompositions. The tolerance for each decomposition can be changed separately. The following operators are affected by a change in the tolerance:

## Crout LU Decomposition

`crout(x)`  
`croutp(x)`  
`inv(x)`  
`det(x)`  
 $y/x$

when neither  $x$  nor  $y$  is scalar and  $x$  is square.

## Cholesky Decomposition

`chol(x)`  
`invpd(x)`  
`solpd(y,x)`  
 $y/x$

when neither  $x$  nor  $y$  is scalar and  $x$  is not square.

## C.1 Reading and Setting the Tolerance

The tolerance value may be read or set using the **sysstate** function, cases 13 and 14.

## C.2 Determining Singularity

There is no perfect tolerance for determining singularity. The default is 1.0e-14. You can adjust this as necessary.

A numerically better method of determining singularity is to use **cond** to determine the condition number of the matrix. If the equation

$$1 / \text{cond}(\mathbf{x}) + 1 \text{ eq } 1$$

is true, then the matrix is usually considered singular to machine precision. (See LINPACK for a detailed discussion on the relationship between the matrix condition and the number of significant figures of accuracy to be expected in the result.)

# Index

- / , 11-8
- ./ , 11-8
- ~ , 11-9
- | , 11-8
- ! , 11-6
- % , 11-5
- \* , 11-5
- \*~ , 11-7
- .\* , 11-6
- .\*. , 11-6
- + , 11-4
- , 11-4
- / , 11-5
- ./ , 11-6
- ^ , 11-6, 11-19
- .^ , 11-6
- , (comma) , 11-16
- . (dot) , 11-16
- : (colon) , 11-17
- ; (semicolon) , 10-2
- # , 21-3, 28-112, 28-113, 28-493, 28-653, 28-875
- \$ , 28-112, 28-113, 28-493, 28-653, 28-875
- ~ , 11-19
- \$| , 11-19
- \$+ , 11-18
- & , 11-17, 12-10
- = , 10-2, 10-12, 10-39
- = , 11-16
- / = , 11-11
- ./= , 11-12
- == , 10-40, 11-11
- == , 11-12
- > , 11-11
- .> , 11-13
- >= , 11-11
- .>= , 11-12
- < , 11-10
- .< , 11-12
- <= , 11-10
- .<= , 11-12
- \_\_altnam, 28-227
- \_\_output, 28-227, 28-482, 28-769
- \_\_title, 28-227
- \_\_Tol, 28-227
- \_eqs\_IterInfo, 28-227
- \_eqs\_JacobianProc, 28-227
- \_eqs\_MaxIters, 28-227
- \_eqs\_StepTol, 28-227
- \_eqs\_TypicalF, 28-227
- \_eqs\_TypicalX, 28-227
- \_loess\_Degree, 28-482

Index

\_loess\_NumEval, 28-482  
 \_loess\_Span, 28-482  
 \_loess\_WgtType, 28-482  
 \_sparse\_Acond], 28-758  
 \_sparse\_Anorm, 28-758  
 \_sparse\_ARnorm], 28-758  
 \_sparse\_Atol, 28-757  
 \_sparse\_Btol, 28-757  
 \_sparse\_CondLimit, 28-757  
 \_sparse\_Damping, 28-757  
 \_sparse\_NumIters, 28-757  
 \_sparse\_RetCode, 28-758  
 \_sparse\_XAnorm], 28-758  
 \_sqp\_A, 28-766  
 \_sqp\_B, 28-766  
 \_sqp\_Bounds, 28-767  
 \_sqp\_C, 28-767  
 \_sqp\_D, 28-767  
 \_sqp\_DirTol, 28-768  
 \_sqp\_EqProc, 28-766  
 \_sqp\_FeasibleTest, 28-768  
 \_sqp\_GradProc, 28-767  
 \_sqp\_HessProc, 28-768  
 \_sqp\_IneqProc, 28-767  
 \_sqp\_MaxIters, 28-768  
 \_sqp\_ParNames, 28-768  
 \_sqp\_PrintIters, 28-768  
 \_sqp\_RandRadius, 28-769

## A

---

abs, 28-1  
 absolute value, 28-1  
 acf, 28-2  
 aconcat, 16-4, 28-3  
 additive sequence, 28-727  
 aeye, 16-6, 28-5  
 algebra, linear, 27-4

amax, 16-25, 28-6  
 amean, 16-25, 28-8  
 AmericanBinomCall, 28-10  
 AmericanBinomCall\_Greeks, 28-11  
 AmericanBinomCall\_ImpVol, 28-13  
 AmericanBinomPut, 28-14  
 AmericanBinomPut\_Greeks, 28-15  
 AmericanBinomPut\_ImpVol, 28-17  
 AmericanBSCall, 28-18  
 AmericanBSCall\_Greeks, 28-19  
 AmericanBSCall\_ImpVol, 28-20  
 AmericanBSPut, 28-21  
 AmericanBSPut\_Greeks, 28-22  
 AmericanBSPut\_ImpVol, 28-23  
 amin, 16-25, 28-24  
 ampersand, 11-17  
 amult, 16-23, 28-26  
 and, 11-13, 11-14  
 .and, 11-15  
 annualTradingDays, 28-28  
 append, ATOG command, 23-3  
 arccos, 28-29  
 arcsin, 28-30  
 areshape, 16-2, 28-31  
 arguments, 10-40, 12-3, 12-7  
 array indexing, 15-3  
 arrayalloc, 16-7, 28-32  
 arrayindex, 28-33  
 arrayinit, 16-6, 28-34  
 arrays, 15-1, 16-1, 27-27  
 arrays of structures, 13-4  
 arraytomat, 16-28, 28-35  
 arrows, 22-14, 22-16  
 ASCII files, 23-1  
 ASCII files, packed, 23-8  
 ASCII files, reading, 19-3  
 ASCII files, writing, 19-4

**asclabel**, 28-36  
 assigning to arrays, 16-8  
 assignment operator, 10-2, 10-39, 11-16  
**asum**, 28-37  
**atan**, 28-39  
**atan2**, 28-40  
 atog, 19-3  
 ATOG, 23-1  
**atranspose**, 16-21, 28-41  
 autoloader, 10-4, 10-5, 17-1, 28-457  
 auxiliary output, 19-4, 28-549  
 auxiliary output, width, 28-552  
 axes, 22-17, 22-19  
 axes numbering, 22-26  
 axes, reversed, 28-897, 28-900  
**axmargin**, 28-43

## B

backslash, 10-21  
**balance**, 28-44  
**band**, 28-46  
**bandchol**, 28-47  
**bandcholsol**, 28-48  
**bandltsol**, 28-49  
**bandrv**, 28-51  
**bandsolpd**, 28-52  
 bar shading, 22-17  
 bar width, 22-18  
**bar**, 28-53  
**base10**, 28-55  
 batch mode, 3-1  
**begwind**, 28-55  
**besselj**, 28-56  
**bessely**, 28-57  
 beta function, 28-62  
 binary file, loading, 28-338  
 binary files, 19-15

bivariate Normal, 28-64  
 blank lines, 10-38  
 bookmarks, 5-2  
 Boolean operators, 11-13  
 box, 22-18  
**box**, 28-57  
**boxcox**, 28-59  
 branching, 27-40  
**break**, 28-60  
 Breakpoints, 5-8  
**browse**, 3-3

## C

**call**, 28-61  
 calling a procedure, 12-6  
 caret, 11-6, 11-19  
 Cartesian coordinates, 28-898  
 case, 10-38, 28-488, 28-858  
**cdfbeta**, 28-62  
**cdfbvn**, 28-64  
**cdfbvn2**, 28-66  
**cdfbvn2e**, 28-67  
**cdfchic**, 28-69  
**cdfchii**, 28-70  
**cdfchinc**, 28-71  
**cdffc**, 28-73  
**cdffnc**, 28-75  
**cdfgam**, 28-75  
 cdfm.src, 28-79, 28-80, 28-81, 28-83,  
     28-85, 28-87  
**cdfmvn**, 28-77  
**cdfmvn2e**, 28-80  
**cdfmvnce**, 28-78  
**cdfmvne**, 28-79  
**cdfmvt2e**, 28-86  
**cdfmvtce**, 28-82  
**cdfmvte**, 28-84

- cdfn**, 28-88
- cdfn2**, 28-90
- cdfnc**, 28-88
- cdfni**, 28-91
- cdftc**, 28-92
- cdftci**, 28-93
- cdftnc**, 28-94
- cdftvn**, 28-95
- cdir**, 28-97
- ceil**, 28-98
- ChangeDir**, 28-99
- characteristic polynomial, 28-561
- chdir**, 28-99
- chi-square, 28-69
- chi-square, noncentral, 28-71
- chol**, 28-100
- choldn**, 28-101
- Cholesky decomposition, 0-1, 11-5, 28-100, 28-743
- cholsol**, 28-102
- cholup**, 28-103
- chrs**, 28-104
- circles, 22-22
- clear**, 28-105
- clearg**, 28-106
- close**, 28-106
- closeall**, 28-108
- cls**, 28-110
- code (dataloop)**, 28-112
- code**, 28-110
- coefficient of determination, 28-529, 28-534
- coefficients, 28-529, 28-534
- coefficients, standardized, 28-529, 28-534
- colon, 10-39
- color, 22-19, 22-25
- Colors, 0-1
- colors, 0-1
- cols**, 28-114
- colsf**, 28-114
- columns in a matrix, 28-114
- combinate**, 28-115
- combined**, 28-116
- comlog**, 28-117
- comma, 11-16
- command, 10-2
- Command Input - Output Window, 5-4
- command line, 3-1
- comments, 10-38
- comparison functions, 28-264, 28-266
- comparison operator, 10-40
- compilation phase, 21-3
- compile**, 18-1
- compile options, 5-11
- compile time, 10-1
- compile**, 28-118
- compiled language, 10-1
- compiler, 18-1
- compiler directives, 27-38
- compiling, 27-43
- compiling files, 18-2
- compiling programs, 18-2
- complex constants, 10-14, 28-165, 28-451, 28-783
- complex modulus, 28-1
- complex**, 23-4, 28-120
- con**, 28-121
- concatenation, matrix, 11-8, 11-9
- concatenation, string, 11-18
- cond**, 28-123
- condition number, 28-123
- conditional branching, 10-34
- config**, 3-3
- conformability, 11-1
- conj**, 28-124

**cons**, 28-125  
constants, complex, 10-14, 28-165, 28-451,  
28-783  
**continue**, 28-125  
contour levels, 22-22  
**contour**, 28-126  
control flow, 10-31  
control structures, 13-22  
**conv**, 28-127  
conversion, character to ASCII value, 28-863  
conversion, float to ASCII, 28-302, 28-303  
conversion, string to floating point, 28-782  
**convertsatostr**, 28-128  
**convertstrtosa**, 28-129  
convolution, 28-127  
coordinates, 22-6  
correlation matrix, 28-129, 28-130, 28-529,  
28-534  
**corrmm**, 28-129  
**corrms**, 28-130  
**corrvc**, 28-129  
**corrxx**, 28-129  
**corrxxs**, 28-130  
**cos**, 28-131  
**cosh**, 28-131  
cosine, inverse, 28-29  
**counts**, 28-132  
**countwts**, 28-134  
**create**, 28-135  
cropping, 22-19  
cross-product, 28-141, 28-514  
**crossprd**, 28-141  
Crout decomposition, 28-142, 28-143  
Crout LU decomposition, 0-1  
**crout**, 28-142  
**croutp**, 28-143  
**csrcol**, 28-145

**csrlin**, 28-145  
**cumprodc**, 28-146  
**cumsumc**, 28-147  
cumulative distribution function, 28-62  
cumulative products, 28-146  
cumulative sums, 28-147  
cursor, 28-145, 28-481  
**curve**, 28-148  
**cvtos**, 28-149

## D

data coding, 27-35  
data handling, 27-30  
data loop, 21-1  
data sets, 19-7, 27-33  
data transformations, 21-1, 28-110, 28-171  
data, writing, 28-883  
**datacreate**, 28-150  
**datacreatecomplex**, 28-152  
**datalist**, 28-154  
**dataload**, 28-155  
**dataloop** translator, 3-3  
**dataloop**, 28-156  
**dataopen**, 28-157  
**datasave**, 28-159  
date, 22-20, 28-160  
**date**, 28-160  
**datestr**, 28-160  
**datestring**, 28-161  
**datestrymd**, 28-162  
**dayinyr**, 28-162  
**dayofweek**, 28-163  
**debug**, 28-164  
Debugger, 5-7  
debugging, 3-4, 18-3, 27-46, 28-459  
**declare**, 28-164  
**delete (dataloop)**, 28-170

**delete**, 28-169  
**DeleteFile**, 28-171  
deletion, 28-198, 28-199, 28-514, 28-554  
**delif**, 28-171  
delimited, 23-1  
delimited files, 19-3  
delimited, hard, 23-6  
delimited, soft, 23-5  
**denseSubmat**, 28-172  
derivatives, 28-357  
derivatives, second partial, 28-374  
descriptive statistics, 28-197, 28-198  
design matrix, 28-173  
**design**, 28-173  
**det**, 28-174  
determinant, 28-174  
**detl**, 28-175  
**dfft**, 28-176  
**dffti**, 28-177  
**diag**, 28-178  
diagonal, 28-178  
**diagrv**, 28-179  
differentiation, 27-3  
**digamma**, 28-180  
dimension index, 15-2  
dimension number, 15-2  
directory, 28-97  
division, 11-5  
**dlibrary**, 20-1, 28-180  
**dllcall**, 20-1, 28-182  
**do loop**, 10-32  
**do until**, 28-183  
**do while**, 28-183  
**dos**, 28-186  
**doswin**, 28-188  
**DOSWinCloseall**, 28-188  
**DOSWinOpen**, 28-189  
dot relational operator, 11-11, 11-21  
**dotmtfeq**, 28-191  
**dotmtfeqmt**, 28-193  
**dotfge**, 28-191  
**dotfgemt**, 28-193  
**dotfgt**, 28-191  
**dotfgtmt**, 28-193  
**dotfle**, 28-191  
**dotflemt**, 28-193  
**dotflt**, 28-191  
**dotflmt**, 28-193  
**dotfne**, 28-191  
**dotfnemt**, 28-193  
downloading, 2-2  
**draw**, 28-194  
**drop (dataloop)**, 28-195  
DS structure, 13-15, 14-7  
**dsCreate**, 28-196  
**dstat**, 28-197  
**dstatmt**, 28-198  
**dstatmtControlCreate**, 28-201  
**dtdate**, 28-201  
**dtday**, 28-202  
**dttime**, 28-202  
**dttodtv**, 28-203  
**dttostr**, 28-204  
**dttoutc**, 28-206  
**dtvnormal**, 28-207  
**dtvtodt**, 28-208  
**dtvtoutc**, 28-209  
dummy variables, 28-210  
**dummy**, 28-210  
**dummybr**, 28-212  
**dummydn**, 28-213  
Durbin-Watson statistic, 28-528, 28-532  
dynamic libraries, 20-3



## E

E×E conformable, 11-1

**ed**, 28-215

edit windows, 5-1

**edit**, 28-216

editing matrices, 6-1

editor, 28-216

editor properties, 5-2

editor, alternate, 28-215

Editor, Matrix, 6-1

**eig**, 28-216

eigenvalues, 27-9, 28-216

eigenvalues and eigenvectors, 28-220

**eigh**, 28-218

**eighv**, 28-219

**eigv**, 28-220

**elapsedTradingDays**, 28-221

element-by-element conformability, 11-1,  
15-5

element-by-element operators, 11-1

**else**, 28-379

**elseif**, 28-379

empty matrix, 10-15, 28-114, 28-452,  
28-473, 28-705, 28-718

end of file, 28-225

**end**, 28-222

**endp**, 12-2, 12-5, 28-223

**endwind**, 28-224

**envget**, 28-224

environment, search, 28-224

**eof**, 28-225

**eq**, 11-11

**.eq**, 11-12

**eqSolve**, 28-226

**eqSolveSet**, 28-230

**eqSolveSetControlCreate**, 28-234

**eqSolveSetOutCreate**, 28-235

**eqSolveSet**, 28-235

**eqv**, 11-14, 11-15

**.eqv**, 11-15

**erf**, 28-236

**erfc**, 28-236

error bar, 22-20

error code, 28-237, 28-717

error function, 28-236

error handling, 27-46

error messages, 24-1, 28-238, 28-459

Error Output Window, 5-7

error trapping, 28-843

**error**, 28-237

**errorlog**, 28-238

escape character, 10-21

**etdays**, 28-239

**ethsec**, 28-240

**etstr**, 28-241

**EuropeanBinomCall**, 28-241

**EuropeanBinomCall\_Greeks**, 28-243

**EuropeanBinomCall\_ImpVol**, 28-244

**EuropeanBinomPut**, 28-245

**EuropeanBinomPut\_Greeks**, 28-246

**EuropeanBinomPut\_ImpVol**, 28-248

**EuropeanBSCall**, 28-249

**EuropeanBSCall\_Greeks**, 28-250

**EuropeanBSCall\_ImpVol**, 28-251

**EuropeanBSPut**, 28-252

**EuropeanBSPut\_Greeks**, 28-253

**EuropeanBSPut\_ImpVol**, 28-255

**exctsmpl**, 28-256

**exec**, 28-257

**execbg**, 28-258

executable code, 10-4

executable statement, 10-3

execution phase, 21-4

## Index

---

execution time, 10-1  
**exp**, 28-259  
exponential function, 28-259  
exponentiation, 11-6  
expression, 10-1  
expression, evaluation order, 10-29  
expression, scalar, 10-32  
**extern (dataloop)**, 28-259  
**external**, 28-260  
extraneous spaces, 10-38  
**eye**, 28-262

## F

---

*F* distribution, 28-73, 28-75  
factorial, 11-6  
FALSE, 10-32  
**fcheckerr**, 28-263  
**fclearerr**, 28-263  
**feq**, 28-264  
**feqmt**, 28-266  
**fflush**, 28-267  
fft, 28-268  
**fft**, 28-268  
**ffti**, 28-269  
**fftm**, 28-270  
**fftmi**, 28-272  
**fftn**, 28-275  
**fge**, 28-264  
**fgemt**, 28-266  
**fgets**, 28-276  
**fgetsa**, 28-277  
**fgetsat**, 28-278  
**fgetst**, 28-279  
**fgt**, 28-264  
**fgtmt**, 28-266  
file formats, 19-14  
file handle, 28-138, 28-542

**fileinfo**, 28-279  
files, 19-3  
files, binary, 19-15  
files, matrix, 19-13  
files, string, 19-16  
**filesa**, 28-281  
finance functions, 27-20  
**fle**, 28-264  
**flemt**, 28-266  
**floor**, 28-282  
flow control, 10-31  
**flt**, 28-264  
**flmt**, 28-266  
**fmod**, 28-283  
**fn**, 28-283  
**fne**, 28-264  
**fnemt**, 28-266  
fonts, 0-1, 28-284  
**fonts**, 28-284  
**fopen**, 28-285  
**for**, 28-286  
Foreign Language Interface, 20-1  
**format**, 28-288  
**formatcv**, 28-295  
**formatnv**, 28-296  
forward reference, 17-2  
Fourier transform, 28-268  
Fourier transform, discrete, 28-177  
fourier transforms, 27-10  
**fputs**, 28-297  
**fputst**, 28-298  
**fseek**, 28-299  
**fstrerror**, 28-300  
**ftell**, 28-301  
**ftocv**, 28-302  
**ftos**, 28-303  
**ftostrC**, 28-306

function, 10-37, 28-425, 28-582  
 functions, 27-42  
 fuzzy conditional functions, 27-12

## G

gamma function, 28-307  
**gamma**, 28-307  
 gamma, incomplete, 28-75  
 gamma, log, 28-467  
**gammaii**, 28-308  
 GAUSS Data Archives, 19-11, 19-24, 27-31  
 GAUSS Source Browser, 8-1  
 Gauss-Legendre quadrature, 28-406  
**gausset**, 26-6, 28-309  
**gdaAppend**, 28-309  
**gdaCreate**, 28-311  
**gdaDStat**, 28-312  
**gdaDStatMat**, 28-314  
**gdaGetIndex**, 28-317  
**gdaGetName**, 28-317  
**gdaGetNames**, 28-318  
**gdaGetOrders**, 28-319  
**gdaGetType**, 28-320  
**gdaGetTypes**, 28-321  
**gdaGetVarInfo**, 28-322  
**gdaIsCplx**, 28-323  
**gdaPack**, 28-324  
**gdaRead**, 28-325  
**gdaReadByIndex**, 28-326  
**gdaReadSome**, 28-327  
**gdaReportVarInfo**, 28-328  
**gdaUpdate**, 28-329  
**gdaUpdateAndPack**, 28-331  
**gdaWrite**, 28-332  
**gdaWrite32**, 28-333  
**gdaWriteSome**, 28-334  
**ge**, 11-11

**.ge**, 11-12  
 generalized inverse, 28-417, 28-558, 28-559  
**getarray**, 28-337  
**getArray**, 16-12  
**getdims**, 28-337  
**getDims**, 16-27  
**getf**, 28-338  
**getmatrix**, 28-339  
**getMatrix**, 16-13  
**getmatrix4D**, 28-340  
**getMatrix4D**, 16-13  
**getname**, 28-341  
**getnamef**, 28-342  
**getNextTradingDay**, 28-343  
**getNextWeekDay**, 28-344  
**getnr**, 28-344  
**getnrmt**, 28-345  
**getOrders**, 16-27  
**getorders**, 28-346  
**getpath**, 28-347  
**getPreviousTradingDay**, 28-347  
**getPreviousWeekDay**, 28-348  
**getScalar3D**, 16-14  
**getscalar3D**, 28-348  
**getScalar4D**, 16-14  
**getscalar4D**, 28-349  
**getwind**, 28-350  
 global control variables, 26-5  
 global variable, 12-3  
 Goertzel algorithm, 28-177  
**gosub**, 28-351  
**goto**, 28-354  
 gradient, 28-357  
**gradMT**, 28-355  
**gradMTm**, 28-356  
**gradp**, 28-357  
 graphic panels, 22-7

## Index

---

graphic panels, nontransparent, 22-8  
graphic panels, overlapping, 22-7  
graphic panels, tiled, 22-7  
graphic panels, transparent, 22-8  
graphics, publication quality, 22-1  
**graphprt**, 28-359  
**graphset**, 28-361  
grid, 22-21  
grid subdivisions, 22-21  
**gt**, 11-11  
**.gt**, 11-13

## H

---

hard delimited, 23-6  
**hasimag**, 28-362  
hat operator, 11-6, 11-19  
**header**, 28-363  
**headermt**, 28-364  
help, 9-1  
help facility, 28-459  
hermitian matrix, 28-219  
**hess**, 28-365  
Hessian, 28-374  
**hessMT**, 28-366  
**hessMTg**, 28-367  
**hessMTgw**, 28-368  
**hessMTm**, 28-370  
**hessMTmw**, 28-371  
**hessMTw**, 28-372  
**hessp**, 28-374  
hidden lines, 22-27  
**hist**, 28-375  
**histf**, 28-376  
histogram, 28-375, 28-376  
**histp**, 28-377  
horizontal direct product, 11-7  
**hsec**, 28-378

hyperbolic cosine, 28-131  
hyperbolic sine, 28-741  
hyperbolic tangent, 28-831

## I

---

**if**, 28-379  
**imag**, 28-380  
imaginary matrix, 28-380  
inch coordinates, 22-6  
**#include**, 28-381  
incomplete beta function, 28-62  
incomplete gamma function, 28-75  
**indcv**, 28-382  
indefinite, 10-27  
index variables, 28-542  
**indexcat**, 28-383  
indexing matrices, 10-40, 11-17  
indexing procedures, 11-17  
indexing, array, 15-3  
indexing, structure, 13-5  
**indices**, 28-385  
**indices2**, 28-386  
**indicesf**, 28-387  
**indicesfn**, 28-388  
**indnv**, 28-389  
**indsav**, 28-390  
infinity, 10-27  
initialize, 12-4  
initializing arrays, 16-1  
inner product, 11-5  
**input**, ATOG command, 23-4  
input, console, 28-121  
input, keyboard, 28-121  
installation, 2-1  
installation, UNIX/Linux, 2-1  
installation, Windows, 2-2  
instruction pointer, 10-3

integration, 27-3, 27-4, 28-395, 28-398,  
     28-400, 28-403, 28-406, 28-414  
 interactive commands, 3-2  
 interpreter, 10-1  
 intersection, 28-413  
**intgrat2**, 28-391  
**intgrat3**, 28-393  
**inthp1**, 28-395  
**inthp2**, 28-397  
**inthp3**, 28-400  
**inthp4**, 28-403  
**inthpControlCreate**, 28-406  
**intquad1**, 28-406  
**intquad2**, 28-408  
**intquad3**, 28-409  
 intrinsic function, 10-8  
**intrleav**, 28-411  
**intrleavsa**, 28-412  
**intrsect**, 28-413  
**intrsectsa**, 28-414  
**intsimp**, 28-414  
**inv**, 28-415  
**invar**, ATOG command, 23-5  
 inverse cosine, 28-29  
 inverse sine, 28-30  
 inverse, generalized, 28-417, 28-558, 28-559  
 inverse, matrix, 28-415  
 inverse, sweep, 28-417  
**invpd**, 28-415  
**invswp**, 28-417  
**iscplx**, 28-418  
**iscplxsf**, 28-419  
**isinfnanmiss**, 28-419  
**issmiss**, 28-420  
**isSparse**, 28-420

## J

---

Jacobian, 28-357

## K

---

**keep (dataloop)**, 28-421  
**key**, 28-421  
**keyav**, 28-424  
 keyboard input, 28-125  
 keyboard, reading, 28-422  
 keys, command, 5-17  
 keys, edit, 5-16  
 keys, function, 5-18  
 keys, menu, 5-19  
 keys, movement, 5-15  
 keys, text selection, 5-17  
 keystroke macros, 5-2  
**keyw**, 28-424  
 keyword, 12-1, 12-7  
 keyword procedure, 28-425  
**keyword**, 28-424  
 keywords, 27-42  
 Kronecker, 11-6

## L

---

label, 10-35, 10-39, 12-1, 28-351, 28-354  
**lag (dataloop)**, 28-426  
**lag1**, 28-426  
**lagn**, 28-427  
 lambda, 28-72  
**lapeighb**, 28-428  
**lapeighi**, 28-429  
**lapeigvb**, 28-430  
**lapeigvi**, 28-432  
**lapgeig**, 28-433  
**lapgeigh**, 28-434  
**lapgeighv**, 28-435

**lapgeigv**, 28-436  
**lapgschur**, 28-445  
**lapgsvdcst**, 28-437  
**lapgsvds**, 28-440  
**lapgsvdst**, 28-442  
**lapsvdcusv**, 28-446  
**lapsvds**, 28-448  
**lapsvdusv**, 28-449  
**le**, 11-10  
**.le**, 11-12  
least squares, 11-5  
least squares regression, 28-526, 28-531  
left-hand side, 17-2  
legend, 22-22  
**let**, 28-450  
**lib**, 28-455  
libraries, 17-1, 27-43  
libraries, active, 28-457  
Library Tool, 7-1  
**library**, 28-456  
line numbers, 28-459  
line thickness, 22-16, 22-20, 22-25  
line type, 22-25  
linear algebra, 27-4  
linear equation, 28-743  
linear equation solution, 11-5  
lines, 22-21, 22-22, 22-24  
**#linesoff**, 28-459  
**#lineson**, 28-459  
**linsolve**, 28-460  
**listwise (dataloop)**, 28-461  
listwise deletion, 28-197, 28-199, 28-514, 28-554  
literal, 10-22, 11-19  
**ln**, 28-461  
**lncdfbvn**, 28-462  
**lncdfbvn2**, 28-463  
**lncdfmvn**, 28-465  
**lncdfn**, 28-465  
**lncdfn.src**, 28-78, 28-91  
**lncdfn2**, 28-466  
**lncdfnc**, 28-467  
**lnfact**, 28-467  
**lnpdfmvn**, 28-468  
**lnpdfmvmt**, 28-469  
**lnpdfn**, 28-470  
**lnpdfft**, 28-470  
**load**, 28-471  
**loadarray**, 28-476  
**loadadd**, 28-478  
**loadf**, 28-471  
**loadk**, 28-471  
**loadm**, 28-471  
**loadp**, 28-471  
**loads**, 28-471  
**loadstruct**, 28-479  
**loadwind**, 28-479  
local variable declaration, 12-3  
local variables, 10-8, 12-3, 28-480  
**local**, 12-2, 28-480  
**locate**, 28-481  
**loess**, 28-481  
**loessmt**, 28-482  
**loessmtControlCreate**, 28-483  
log coordinates, 28-485  
log factorial, 28-467  
log gamma, 28-467  
**log**, 28-484  
log, base 10, 28-484  
log, natural, 28-461  
logging commands, 28-117  
logical operators, 11-13  
**loglog**, 28-485  
**logx**, 28-485

**logy**, 28-486  
 looping, 10-31, 27-40, 28-183  
 looping with arrays, 16-17  
**loopnextindex**, 16-19, 28-487  
 lower triangular matrix, 28-489  
**lower**, 28-488  
**lowmat**, 28-489  
**lowmat1**, 28-489  
**lt**, 11-10  
**.lt**, 11-12  
**ltrisol**, 28-490  
 LU decomposition, 11-5, 28-491  
**lu**, 28-491  
**lusol**, 28-492

## M

**machEpsilon**, 28-492  
 machine epsilon, 28-88, 28-823, 28-828  
 machine requirements, 2-2  
 macros, 5-2  
 magnification, 22-29  
**make (dataloop)**, 28-493  
**makevars**, 28-493  
**makewind**, 28-495  
**margin**, 28-496  
**matalloc**, 28-497  
**matinit**, 28-498  
 matrices, indexing, 10-40  
 matrix conformability, 11-1  
 Matrix Editor, 6-1  
 matrix files, 19-13  
 matrix manipulation, 27-22  
 matrix, creation, 28-450  
 matrix, empty, 10-15, 28-114, 28-452,  
     28-473, 28-705, 28-718  
 matrix, ones, 28-540  
 matrix, zeros, 28-900

**mattoarray**, 16-28, 28-498  
**maxbytes**, 28-502  
**maxc**, 28-499  
 maximizing performance, 25-1  
 maximum element, 28-499  
 maximum element index, 28-500  
**maxindc**, 28-500  
**maxvec**, 28-501  
**mbesseli**, 28-503  
 mean, 28-506  
**meanc**, 28-506  
**median**, 28-506  
 memory, 28-169  
 memory, clear all, 28-520  
 menus, 4-1  
**mergeby**, 28-507  
**mergevar**, 28-508  
 merging, 27-37  
**minc**, 28-509  
 minimum element, 28-509  
 minimum element index, 28-510  
**minindc**, 28-510  
**miss**, 28-511  
**missex**, 28-513  
 missing character, 28-519  
 missing values, 11-5, 28-197, 28-199,  
     28-420, 28-511, 28-513, 28-519,  
     28-554, 28-720  
**missrv**, 28-511  
 modulo division, 11-5  
 moment matrix, 28-514, 28-528, 28-533  
**moment**, 28-514  
**momentd**, 28-515  
 Moore-Penrose pseudo-inverse, 28-558,  
     28-559  
**movingave**, 28-517  
**movingaveExpwgt**, 28-517

## Index

---

**movingaveWgt**, 28-518  
**msym**, 28-519  
**msym**, ATOG command, 23-10  
multiplication, 11-5  
multiplicative sequence, 28-727

## N

---

N-dimensional arrays, 15-1, 16-1, 27-27  
NaN, 10-27, 10-28  
NaN, testing for, 10-28, 11-9  
**ne**, 11-11  
**.ne**, 11-12  
**new**, 28-519  
**nextindex**, 28-521  
**nextn**, 28-522  
**nextnevn**, 28-522  
**nextwind**, 28-523  
**nocheck**, 23-10  
Normal distribution, 28-77, 28-78, 28-79,  
28-80, 28-82, 28-84, 28-86, 28-88,  
28-90, 28-462, 28-465, 28-466,  
28-467  
Normal distribution, bivariate, 28-64  
**not**, 11-13, 11-14  
**.not**, 11-15  
null space, 28-524  
**null**, 28-524  
**null1**, 28-525  
**numCombinations**, 28-526

## O

---

obsolete commands, 0-1  
**ols**, 28-526  
**olsmt**, 28-531  
**olsmtControlCreate**, 28-536  
**olsqr**, 28-537

**olsqr2**, 28-538  
**olsqrmt**, 28-539  
**ones**, 28-540  
**open**, 28-540  
operators, 10-1, 11-4  
operators, element-by-element, 11-1  
optimization, 27-16  
**optn**, 28-546  
**optnevn**, 28-546  
**or**, 11-14, 11-15  
**.or**, 11-15  
**orth**, 28-548  
orthogonal complement, 28-524  
orthonormal, 28-524, 28-548  
outer product, 11-6  
output, 19-4  
output functions, 27-52  
**output**, 28-548  
**output**, ATOG command, 23-10  
**outtyp (dataloop)**, 28-552  
**outtyp**, ATOG command, 23-11  
**outvar**, ATOG command, 23-11  
**outwidth**, 28-552

## P

---

**pacf**, 28-553  
packed ASCII, 23-1, 23-8  
**packr**, 28-554  
**\_pageshf**, 22-14  
**\_pagesiz**, 22-14  
pairwise deletion, 11-5, 28-198, 28-199,  
28-514  
panel data, 16-32  
**\_parrow**, 22-14  
**\_parrow3**, 22-16  
**parse**, 28-556  
**pause**, 28-556



- 
- \_paxes**, 22-17
  - \_paxht**, 22-17
  - \_pbartyp**, 22-17
  - \_pbarwid**, 22-18
  - \_pbox**, 22-18
  - \_pboxlim**, 22-19
  - \_pcolor**, 22-19
  - \_pcrop**, 22-19
  - \_pcross**, 22-19
  - \_pdate**, 22-20
  - pdfn**, 28-557
  - \_perrbar**, 22-20
  - \_pframe**, 22-20
  - \_pgrid**, 22-21
  - pi**, 28-557
  - pinv**, 28-558
  - pinvmt**, 28-559
  - pixel coordinates, 22-6
  - \_plctrl**, 22-21
  - \_plegctl**, 22-22
  - \_plegstr**, 22-22
  - \_plev**, 22-22
  - \_pline**, 22-22
  - \_pline3d**, 22-24
  - plot coordinates, 22-6
  - \_plotshf**, 22-24
  - \_plotsiz**, 22-25
  - \_pltype**, 22-25
  - \_plwidth**, 22-25
  - \_pmcolor**, 22-25
  - \_pmsgctl**, 22-26
  - \_pmsgstr**, 22-26
  - \_pnotify**, 22-26
  - \_pnum**, 22-26
  - \_pnumht**, 22-27
  - pointer, 11-17, 12-10, 12-11, 28-480
  - pointer, instruction, 10-3
  - pointers, structure, 13-10
  - polar**, 28-560
  - polychar**, 28-561
  - polyeval**, 28-561
  - polyint**, 28-562
  - polymake**, 28-563
  - polymat**, 28-564
  - polymroot**, 28-565
  - polymult**, 28-566
  - polynomial, 28-563
  - polynomial interpolation, 28-562
  - polynomial operations, 27-9
  - polynomial regression, 28-564
  - polynomial, characteristic, 28-561
  - polynomial, evaluation, 28-561
  - polynomial, roots, 28-567
  - polyroot**, 28-567
  - pop**, 28-568
  - pqgwin**, 28-569
  - precedence, 10-29
  - precision control, 27-19
  - predicted values, 28-538
  - preferences, 5-10
  - preservecase**, 23-12
  - previousindex**, 28-569
  - princomp**, 28-570
  - print**, 28-571
  - printdos**, 28-577
  - printfm**, 28-578
  - printfmt**, 28-581
  - probability density function, Normal, 28-557
  - proc**, 12-2, 28-582
  - procedure, 12-1, 28-480, 28-582
  - procedure, definitions, 10-3, 12-2
  - procedures, 27-42
  - procedures, indexing, 12-10
  - procedures, multiple returns, 12-11
-

procedures, passing to other procedures, 12-9  
**prodc**, 28-583  
products, 28-584  
program, 10-4  
program control, 27-39  
program space, 28-737  
program, run, 28-707  
properties, editor, 5-2  
**\_protate**, 22-27  
**\_pscreen**, 22-27  
pseudo-inverse, 28-558, 28-559  
**\_psilent**, 22-27  
**\_pstype**, 22-27  
**\_psurf**, 22-27  
**\_psym**, 22-28  
**\_psym3d**, 22-28  
**\_psymsiz**, 22-28  
**\_ptek**, 22-28  
**\_pticout**, 22-28  
**\_ptitlht**, 22-28  
**Publication Quality Graphics**, 22-1, 27-53  
**putArray**, 16-15  
**putarray**, 28-584  
**putf**, 28-585  
**PV** structure, 13-16, 14-1  
**pvCreate**, 28-587  
**\_pversno**, 22-29  
**pvGetIndex**, 28-587  
**pvGetParNames**, 28-588  
**pvGetParVector**, 28-589  
**pvLength**, 28-590  
**pvList**, 28-590  
**pvPack**, 28-591  
**pvPacki**, 28-592  
**pvPackm**, 28-593  
**pvPackmi**, 28-594  
**pvPacks**, 28-595

**pvPacksi**, 28-597  
**pvPacksm**, 28-598  
**pvPacksmi**, 28-600  
**pvPutParVector**, 28-602  
**pvTest**, 28-603  
**pvUnpack**, 28-604  
**\_pxpmax**, 22-29  
**\_pxsci**, 22-29  
**\_pypmax**, 22-29  
**\_pysci**, 22-29  
**\_pzclr**, 22-29  
**\_pzoom**, 22-29  
**\_pzpmax**, 22-29  
**\_pzsci**, 22-29

## Q

---

**QNewton**, 28-604  
**QNewtonmt**, 28-607  
**QNewtonmtControlCreate**, 28-612  
**QNewtonmtOutCreate**, 28-612  
**QNewtonSet**, 28-613  
**QProg**, 28-613  
**QProgmt**, 28-615  
**QProgmtInCreate**, 28-617  
**qqr**, 28-617  
**qqre**, 28-619  
**qqrep**, 28-622  
QR decomposition, 28-537, 28-539  
**qr**, 28-624  
**qre**, 28-625  
**qrep**, 28-628  
**qrsol**, 28-630  
**qrtsol**, 28-631  
**qtyr**, 28-631  
**qtyre**, 28-634  
**qtyrep**, 28-637  
quadrature, 28-406

**quantile**, 28-639  
**quantiled**, 28-640  
**qyr**, 28-642  
**qyre**, 28-643  
**qyrep**, 28-645

## R

**radii**, 22-22  
**random numbers**, 27-10  
**rank of a matrix**, 28-647  
**rank**, 28-647  
**rankindx**, 28-648  
**readr**, 28-649  
**real**, 28-650  
**recode (dataloop)**, 28-653  
**recode**, 28-651  
**recserar**, 28-654  
**recsercp**, 28-656  
**recserrc**, 28-657  
**recursion**, 12-5  
**reduced row echelon form**, 28-706  
**regression**, 28-526, 28-531  
**relational operator, dot**, 11-11, 11-21  
**relational operators**, 11-9  
**relative error**, 28-88, 28-93  
**rerun**, 28-658  
**reserved words**, 0-1  
**reshape**, 28-659  
**residuals**, 28-528, 28-532, 28-538  
**retp**, 12-2, 12-5, 28-660  
**return**, 28-661  
**rev**, 28-661  
**rfft**, 28-662  
**rffti**, 28-663  
**rfftip**, 28-664  
**rfftn**, 28-665  
**rfftnp**, 28-666  
**rfftp**, 28-668  
**right-hand side**, 17-2  
**rndbeta**, 28-669  
**rndcon**, 28-670  
**rndgam**, 28-672  
**rndi**, 28-673  
**rndKMbeta**, 28-674  
**rndKMgam**, 28-675  
**rndKMi**, 28-677  
**rndKMn**, 28-678  
**rndKMnb**, 28-680  
**rndKMp**, 28-681  
**rndKMu**, 28-682  
**rndKMvm**, 28-684  
**rndLCbeta**, 28-685  
**rndLCgam**, 28-686  
**rndLCi**, 28-688  
**rndLCn**, 28-690  
**rndLCnb**, 28-692  
**rndLCp**, 28-694  
**rndLCu**, 28-695  
**rndLCvm**, 28-697  
**rndmult**, 28-670  
**rndn**, 28-699  
**rndnb**, 28-700  
**rndp**, 28-701  
**rndseed**, 28-670  
**rndu**, 28-701  
**rndvm**, 28-703  
**rotater**, 28-703  
**round down**, 28-282  
**round up**, 28-98  
**round**, 28-704  
**rows**, 28-705  
**rowsf**, 28-706  
**rref**, 28-706  
**rules of syntax**, 10-37

## Index

---

run options, 5-11

**run**, 28-707

Run-Time Library structures, 14-1

running commands, 5-4

running programs, 5-5

## S

---

**satostrC**, 28-709

**save**, 28-710

**saveall**, 28-712

**saved**, 28-713

**savestruct**, 28-714

**savewind**, 28-715

saving the workspace, 18-2

scalar error code, 28-237, 28-717

scalar expression, 10-32

**scale**, 28-715

**scale3d**, 28-716

**scalerr**, 28-717

**scalinfnanmiss**, 28-719

scaling, 28-715, 28-716

**scalmiss**, 28-720

**schtoc**, 28-721

**schur**, 28-722

scientific functions, 27-1

**screen**, 28-723

**searchsourcepath**, 28-724

secondary section, 10-5

**seekr**, 28-725

**select (dataloop)**, 28-726

**selif**, 28-726

semicolon, 10-2

**seqa**, 28-727

**seqm**, 28-727

sequence function, 28-727

sequence functions, 27-19

series functions, 27-19

set difference function, 28-730

**setArray**, 16-16

**setarray**, 28-729

**setdif**, 28-730

**setdifsa**, 28-731

**setvars**, 28-732

**setvwrmode**, 28-733

**setwind**, 28-733

**shell**, 28-734

**shiftr**, 28-735

**show**, 28-736

Simpson's method, 28-414

**sin**, 28-739

sine, inverse, 28-30

**singleindex**, 28-740

singular value decomposition, 28-809,  
28-810, 28-811, 28-813

singular values, 28-808, 28-812

singularity tolerance, 0-1

**sinh**, 28-741

**sleep**, 28-742

soft delimited, 23-5

**solpd**, 28-743

sort data file, 28-746

sort index, 28-748

sort, heap sort, 28-747

sort, multiple columns, 28-749

sort, quicksort, 28-745

**sortc**, 28-745

**sortcc**, 28-745

**sortd**, 28-746

**sorthc**, 28-747

**sorthcc**, 28-747

**sortind**, 28-748

**sortindc**, 28-748

sorting, 27-37

**sortmc**, 28-749

- sortr**, **sortrc**, 28-750
- Source Browser, 8-1
- spaces, 11-17
- spaces, extraneous, 10-38, 11-17
- sparse matrix functions, 27-24
- sparse.src**, 28-173
- sparseCols**, 28-751
- sparseEye**, 28-752
- sparseFD**, 28-752
- sparseFP**, 28-753
- sparseHConcat**, 28-753
- sparseNZE**, 28-754
- sparseOnes**, 28-754
- sparseOnes**, 28-754
- sparseRows**, 28-755
- sparseScale**, 28-755
- sparseSet**, 28-757
- sparseSolve**, 28-757
- sparseSubmat**, 28-759
- sparseTD**, 28-760
- sparseTranspose**, 28-760
- sparseTrTD**, 28-761
- sparseTScalar**, 28-761
- sparseVConcat**, 28-762
- spline**, 28-763
- SpreadsheetReadM**, 28-764
- SpreadsheetReadSA**, 28-764
- spreadsheets, 27-30
- SpreadsheetWrite**, 28-765
- sqpSolve**, 28-766
- sqpSolveMT**, 13-23
- sqpSolveMT**, 28-770
- sqpSolveMTControl structure**, 13-25
- sqpSolveMTControlCreate**, 28-778
- sqpSolveMTlagrangeCreate**, 28-778
- sqpSolveMToutCreate**, 28-779
- sqpSolveSet**, 28-779
- sqrt**, 28-780
- square root, 28-780
- src\_path**, 17-1
- standard deviation, 28-198, 28-200, 28-781
- standard deviation of residual, 28-529, 28-534
- standard errors, 28-529, 28-534
- statement, 10-2, 10-37
- statement, executable, 10-3
- statement, nonexecutable, 10-3
- statistical distributions, 27-17
- statistical functions, 27-13
- statistics, descriptive, 28-197, 28-198
- status bar, 4-15
- stdc**, 28-781
- Stirling's formula, 28-468
- stocv**, 28-782
- stof**, 28-782
- stop**, 28-783
- strcombine**, 28-783
- strindx**, 28-784
- string array concatenation, 11-19
- string arrays, 10-23, 10-25
- string concatenation, 11-18
- string files, 19-16
- string handling, 27-47
- string index, 28-784, 28-787
- string length, 28-785
- string, long, 10-38
- string, substring, 28-788
- strings, graphics, 22-26
- strlen**, 28-785
- strput**, 28-786
- strrindx**, 28-787
- strsect**, 28-788
- strsplit**, 28-789
- strsplitPad**, 28-790

**strtodt**, 28-791  
**strtof**, 28-793  
**strtofcplx**, 28-793  
**strtriml**, 28-794  
**strtrimr**, 28-794  
**strtrunc**, 28-795  
**strtrunc1**, 28-795  
**strtruncpad**, 28-796  
**strtruncr**, 28-796  
structure definition, 13-1  
structure indexing, 13-5  
structure instance, 13-2  
structure pointers, 13-10  
structure, **DS**, 13-15, 14-7  
structure, **PV**, 13-16, 14-1  
structures, 13-1, 27-29  
structures, arrays of, 13-4  
structures, control, 13-22  
**submat**, 28-797  
submatrix, 28-797  
subroutine, 10-36, 28-351  
subroutines, 27-41  
subsample, 28-256  
**subscat**, 28-798  
substitution, 11-19  
substring, 28-788  
**substute**, 28-799  
**subvec**, 28-801  
sum, 28-802  
**sumc**, 28-802  
**sumr**, 28-804  
**surface**, 28-806  
**svd**, 28-808  
**svd1**, 28-809  
**svd2**, 28-810  
**svdcusv**, 28-811  
**svds**, 28-812

**svdusv**, 28-813  
sweep inverse, 28-417  
symbol names, 10-39  
symbol table, 28-736  
symbol table type, 28-848  
symbols, allocate maximum number, 28-520  
syntax, 10-37  
**sysstate**, 28-814  
**system**, 28-829

## T

---

t distribution, Student's, 28-92  
**tab**, 28-829  
table, 11-6  
**tan**, 28-830  
**tanh**, 28-831  
**tempname**, 28-832  
tensor, 11-6  
text files, 27-31  
TGAUSS, 3-1  
thickness, line, 22-16, 22-20, 22-25  
tick marks, 22-28  
tilde, 11-9  
time and date functions, 27-49  
**time**, 28-833  
time, elapsed, 28-239  
**timedt**, 28-833  
**timestr**, 28-834  
**timeutc**, 28-835  
timing functions, 28-378  
**title**, 28-835  
**tkf2eps**, 28-836  
**tkf2ps**, 28-837  
**tocart**, 28-837  
**todaydt**, 28-838  
Toeplitz matrix, 28-838  
**toeplitz**, 28-838

**token**, 28-839  
 toolbars, 4-10  
**topolar**, 28-840  
 trace program execution, 28-841  
**trace**, 28-841  
 translation phase, 21-3  
 transpose, 11-8  
 transpose, bookkeeping, 11-8  
 trap flag, 28-843, 28-845  
 trap state, 28-718  
**trap**, 28-842  
**trapchk**, 28-845  
 triangular matrix, lower, 28-489  
 triangular matrix, upper, 28-857  
**trigamma**, 28-846  
**trimr**, 28-847  
 trivariate Normal, 28-95  
 troubleshooting, libraries, 17-11  
 TRUE, 10-32, 11-10  
**trunc**, 28-848  
 truncating, 28-848  
**type**, 28-848  
**typecv**, 28-849  
**typef**, 28-851

## U

unconditional branching, 10-35  
 underdetermined, 28-529, 28-534  
**union**, 28-852  
**unionsa**, 28-852  
**uniqindx**, 28-853  
**uniqindxsa**, 28-854  
**unique**, 28-855  
**uniquesa**, 28-856  
**until**, 28-183  
**upmat**, 28-857  
**upmat1**, 28-857

upper triangular matrix, 28-857  
**upper**, 28-858  
**use**, 28-859  
 user-defined function, 28-425, 28-582  
**utctodt**, 28-860  
**utctodtv**, 28-861  
**utrisol**, 28-862

## V

**vals**, 28-863  
**varget**, 28-864  
**varget1**, 28-865  
 variable names, 28-341, 28-342  
 variance, 28-198, 28-200  
 variance-covariance matrix, 28-529, 28-534,  
 28-871, 28-872  
 varindx, 28-541  
**varmall**, 28-866  
**varmares**, 28-867  
**varput**, 28-868  
**varput1**, 28-869  
**vartypef**, 28-871  
**vcm**, 28-871  
**vcms**, 28-872  
**vcx**, 28-871  
**vcxs**, 28-872  
**vec**, **vecr**, 28-873  
**vech**, 28-874  
**vector (dataloop)**, 28-875  
 vectors, 10-40  
**vget**, 28-876  
**view**, 28-876  
 viewing graphics, 3-2  
 viewing variables, 6-3  
**viewxyz**, 28-877  
**vlist**, 28-878  
**vnamecv**, 28-878

## Index

---

**volume**, 28-879  
**vput**, 28-879  
**vread**, 28-880  
**vtypecv**, 28-880

## W

---

**wait**, 28-881  
**waitc**, 28-881  
**walkindex**, 28-881  
watch variables, 6-3  
watch window, 5-10  
weighted count, 28-134  
**while**, 28-183  
window, 19-4  
**window**, 28-883  
window, clear, 28-110  
workbox, 28-877, 28-879  
workspace, 28-169, 28-737  
**writer**, 28-883

## X

---

**xlabel**, 28-885  
**xlsGetSheetCount**, 28-886  
**xlsGetSheetSize**, 28-886  
**xlsGetSheetTypes**, 28-887  
**xlsMakeRange**, 28-888  
**xlsreadm**, 28-889  
**xlsreadsa**, 28-890  
**xlsWrite**, 28-892  
**xlsWritem**, 28-893  
**xlswritesa**, 28-894  
**xor**, 11-14, 11-15  
**.xor**, 11-15  
**xpnd**, 28-895  
**xtics**, 28-897  
**xy**, 28-898

**xyz**, 28-898

## Y

---

**ylabel**, 28-899  
**ytics**, 28-899

## Z

---

**zeros**, 28-900  
**zlabel**, 28-901  
zooming graphs, 22-29  
**ztics**, 28-901